



205 Westwood Ave, Long Branch, NJ 07740
Phone: 866-94 BOARDS (26273) / (732)-222-1511
Fax: (732)-222-7088 | E-mail: sales@touchboards.com



Podium View Document Camera Image Software User Manual (WINDOWS)

Contents

1. Introduction.....	2
2. System requirement	2
3. Install Podium View	3
4. Connection	5
5. Start to use Podium View	5
6. Operation.....	6
6.1 Main Menu	6
6.2 Annotation Tools	7
6.3 Camera Settings	8
6.4 Options	9
6.5 Time Lapse	10
7. Descriptions of Functions	11
7.1 Start the Document Camera.....	11
7.2 I would like to display a live image	11
7.3 I would like to optimize the image	11
7.4 I would like to adjust the brightness	11
7.5 I would like to turn on/off the lamp.....	11
7.6 I would like to zoom in/zoom out	11
7.7 I would like to capture images	11
7.8 I would like to freeze the live image	12
7.9 I would like to annotate the displayed image	12
7.10 I would like to add textual annotation to images	13
7.11 I would like to record video.....	14
8. Troubleshooting	16

1.Introduction

After installing the Podium View application, you can use the software to:

- Control the Visual Presenter.
- Capture and record images.
- Annotate images, highlight important details and save them for later use.

2.System requirement

Windows XP

- CPU: P4 2.8 GHz and above
- Memory: 512MB
- Support Direct X 9
- Resolution: 1024x768
- 100MB Min Disc Space
- Windows XP SP2 and above


Windows Vista / 7

- Min CPU: P4 2.8 Ghz
- Min Memory: 1GB (32-bits)/2GB(64-bits)
- Direct X 9 Compatible
- Min Resolution: 1024x768
- 100MB Min Disc Space


2.1 Applicable models: PS750, PS760 and other updated models

3. Install Podium View


1. Please download the **Podium View™** software after connected to the **Lumens™** web site.
2. Click the [**Podium View**] file after decompressing the downloaded file.
3. Select Language.
4. Please follow the installation wizard of Podium View and screen instructions for installation.



5. Press [Yes] to create a Podium View shortcut at your desktop.



6. Once the installation is completed, press [Finish] to reboot the system.




4. Connection



<Very Important> To ensure successful installation, please make sure each of the following steps is completed

- 4.1. Connect the power cord of the Visual Presenter.




<Note> Appearance of power cord and AC outlet may vary with countries/regions.

- 4.2. Turn on the Visual Presenter by pressing the **[POWER]** button on the unit or the remote control for several seconds. When the light next to the power button is lit, the unit is ready to use.



- 4.3. Connect USB cable to the Visual Presenter and your computer.



5. Start to use Podium View

- 5.1. Double-click the **[Podium View]** icon on the desktop to launch Podium View..



- 5.2. Mouse over **[Podium View]** icon to select menu functions.



















- 5.3. Click **[DISPLAY LIVE IMAGES]** icon to start to use.



6. Operation












6.1 Main Menu



	POWER: Turn the visual presenter on / off		LAMP: Turn the lamp on / off
	AUTO TUNE: Automatically adjust the image for best possible quality.		DISPLAY LIVE IMAGES: Display live images
	OPTIONS: Select video compression method and the audio source. For detailed operation instructions, please refer to 6.4 Options .		BRIGHTNESS: Adjust image brightness
	PODIUM VIEW: Launch the main functions menu Right click on this icon to show information about the Podium View.		ZOOM: Zoom in/out from the image
	CAMERA SETTING: Launch the Camera Setting window to adjust live images. For detailed operation instructions, please refer to 6.3 CAMERA Settings .		ADVANCE: Launch the advanced functions menu
	FREEZE: Freeze a live image		ANNOTATION: Display annotation tools For detailed operation instructions, please refer to 6.2 Annotation .
	EXIT: Close the Podium View.		TIME LAPSE CAPTURE: Capture images at a pre-set intervals For detailed operation instructions, please refer to 6.5 Time Lapse
	RECORD VIDEO: Record videos		CAPTURE STILL IMAGES: Capture still images

6.2 Annotation Tools



ICON	Description
	Pointer tool
	Laser tool
	Insert text
	Draw a line
	Draw an ellipse
	Draw a rectangle
	Free-hand drawing tool
	Eraser
	Clear all
	Select pen color
	Select line thickness

6.3 Camera Settings


Control the live image via the **Camera Settings** interface. The operating procedure is the same as the **remote control** and **control panel** of the **Visual Presenter**. Refer to the [Visual Presenter user manual](#) for more information.

<Note> The display of the button may vary depending on product functions. An inactive button will grey out.


- Case 1: for Visual Presenter V2 Module , EX:PS750



- Case 2: for Visual Presenter V3 Module , EX:PS760, CC101.....




6.4 Options



1. **Language:** Set the language.
2. **Factory Reset :** Activate the factory reset.
3. **Video Compress Codec Format :** Set the video format.
<Note> You need to enable the [Enable Video Compress]
4. **Enable Audio Recorder :** Enable the audio record device and set the audio source.
5. **Software mode:** Select the Interactive whiteboard mode / Live mode.

6.5 Time Lapse



The screenshot shows a 'Time Lapse' dialog box with the following fields and controls:

- File Directory:** A text box containing 'C:\Time_Lapse' and a folder icon button. A red circle with the number 1 points to the folder icon.
- File Name:** A text box containing 'Lumens' followed by a template '-YYYY-MM-DD-HH-MM-SS .jpg'. A red circle with the number 2 points to the file name field.
- Select the start time:** A section containing two radio buttons: 'Right Now' and 'Start at'. The 'Start at' option is selected, with a date dropdown set to '2009/07/01' and a time spinner set to '16:48:14'. A red circle with the number 3 points to this section.
- Time Lapse Settings:** A section containing three radio buttons: 'Capture Interval', 'Capture Time', and 'Capture Frame'. The 'Capture Interval' option is selected, with a text box set to '3600' and the unit 'Seconds'. A red circle with the number 4 points to this section.
- Buttons:** 'Ok' and 'Cancel' buttons at the bottom.


1. Select file directory to change the default.
2. Specify a file name.
3. Set the start time.
4. Capture images at a pre-set interval.

7. Descriptions of Functions

7.1 Start the Document Camera

- Click  .


7.2 I would like to display a live image

- Click  to display the live image.

7.3 I would like to optimize the image

- Click  .


7.4 I would like to adjust the brightness

- Click  to show the brightness scroll.
- Move upward to increase brightness, or downward to decrease brightness.


7.5 I would like to turn on/off the lamp

- Click  to turn on/off the lamp.


7.6 I would like to zoom in/zoom out

- Click  to display the image scrollbar.
- Scroll up/down to enlarge/reduce the image.

7.7 I would like to capture images


<NOTE> You can click  to change time lapse setting, more details please refer to [6.5 Time Lapse](#).

- Click  then a Save As window will be displayed.




- Key in the file name then click [Save].

7.8 I would like to freeze the live image

- Click  to freeze the live image of Podium View.

7.9 I would like to annotate the displayed image

- Click  to open the annotation tools.
- The default mode is [Pointer Tool]. You can select another annotation tool.



- Select a color for drawing.



- Set the value of Line width (If the value is higher, the line is thicker).




- Mark or annotate the displayed image.




<Remark> You can Click  to capture images that you draw.

7.10 I would like to add textual annotation to images

- Click  to open the annotation tools.
- Select [Text Tool].



- The [Text Tool] window will pop up when you click the screen for the text to be added in.
- Enter the text in blank fields and click [OK].




- Click [T] to change font's settings (size/color/effect).


<Remark> You can Click  to capture images that you draw.

7.11 I would like to record video


- Click  to open the video tool.

<NOTE> You can click  to change video format and audio source setting, more details please refer to [6.4 Options](#).


- Click [Record] then a window will be displayed.




- Key in the file name then click [Save] to start recording.



- Click [Stop] to stop recording.



- Click  to close the record tool.

8. Troubleshooting

8.1 Q: Black screen is displayed in live image after Podium View was re-installed.

Solution :

1. Remove the Podium View then restart the computer.
2. Re-install the Podium View .

8.2 Q: When running the Podium View , no image is displayed and get a Podium View error message.

“System video limitation reached. Please refer to the troubleshooting section of the Podium View user’s manual.”

Solution :

1. Please check if you are using an extended desktop (two monitors) hooked up to the computer. If so, please try to move the Podium View shortcut to the extended desktop and launch it.
2. If step 1 still doesn't work, please turn off extended desktop.
3. If step 2 still doesn't work, please reduce the resolution of desktop.
4. If step 3 still doesn't work, please reinstall Podium View software.

