

R&S® InstrumentView Software Manual



The software manual describes the following:

- R&S®InstrumentView

The R&S®InstrumentView supports the following product series:

- R&S®FPH
- R&S®ZPH
- R&S®FPC
- R&S®FSH4
- R&S®ZVH
- R&S®FSC

The contents of this manual correspond to software version 1.80 or higher.

The software contained in this product uses several valuable open source software packages. For information, see the "Open Source Acknowledgment" document, which is available for download from the R&S InstrumentView product page at i.e. <http://www.rohde-schwarz.com/product/FPH> > "Downloads" > "Software".

Rohde & Schwarz would like to thank the open source community for their valuable contribution to embedded computing.

© 2018 Rohde & Schwarz GmbH & Co. KG

Mühlhofstr. 15, 81671 München, Germany

Phone: +49 89 41 29 - 0

Fax: +49 89 41 29 12 164

Email: info@rohde-schwarz.com

Internet: www.rohde-schwarz.com

Subject to change – Data without tolerance limits is not binding.

R&S® is a registered trademark of Rohde & Schwarz GmbH & Co. KG.

Trade names are trademarks of the owners.

1321.1040.02 | Version 07.00 | R&S®InstrumentView

Throughout this manual, products from Rohde & Schwarz are indicated without the ® symbol, e.g. R&S®InstrumentView is indicated as R&S InstrumentView.

Customer Support

Technical support – where and when you need it

For quick, expert help with any Rohde & Schwarz equipment, contact one of our Customer Support Centers. A team of highly qualified engineers provides telephone support and will work with you to find a solution to your query on any aspect of the operation, programming or applications of Rohde & Schwarz equipment.

Up-to-date information and upgrades

To keep your instrument up-to-date and to be informed about new application notes related to your instrument, please send an e-mail to the Customer Support Center stating your instrument and your wish. We will take care that you will get the right information.

Europe, Africa, Middle East

Phone +49 89 4129 12345
customersupport@rohde-schwarz.com

North America

Phone 1-888-TEST-RSA (1-888-837-8772)
customer.support@rsa.rohde-schwarz.com

Latin America

Phone +1-410-910-7988
customersupport.la@rohde-schwarz.com

Asia/Pacific

Phone +65 65 13 04 88
customersupport.asia@rohde-schwarz.com

China

Phone +86-800-810-8228 /
+86-400-650-5896
customersupport.china@rohde-schwarz.com



Contents

1	Installing R&S InstrumentView	5
2	R&S InstrumentView Screen Layout	7
3	Connecting the Instrument	10
3.1	Connection Manager Menu	10
4	Using R&S InstrumentView	15
4.1	Printing Trace Windows	15
4.2	Report Generator	17
4.3	Save Instrument	20
4.4	Open Instrument	22
4.5	Working with Trace Windows	22
4.5.1	Get Trace	22
4.5.2	Add Trace	28
4.6	Working with Instrument	29
4.6.1	Remote Display	30
4.6.1.1	Remote Display with Troubleshooting	31
4.6.2	Lab Display	34
4.6.3	File Transfer	34
4.6.4	Synchronization	37
4.6.5	Multi-Transfer	39
4.6.6	Screenshot	42
4.6.7	Date Time Synchronization	43
4.6.8	Save Active Dataset	43
4.6.9	Activate Dataset to Instrument	43
4.6.10	Firmware Update	44
4.7	Working with Instrument Datasets	45
4.7.1	Using Transducers	45
4.7.2	Using Cable Models	47
4.7.3	Calibration Kits	48
4.7.4	Using Limit Lines	49
4.7.5	Using Channel Table	51

4.7.6	Using Standards.....	52
4.7.6.1	Standards Table Editor.....	53
4.7.6.2	Measurement Type.....	53
4.7.7	Using Quick Name Table.....	56
4.7.8	Using Analog Modulation Analysis AM Limits.....	57
4.7.9	Using Analog Modulation Analysis FM Limits.....	58
4.7.10	Wizard Set Editor.....	58
4.7.11	Map Creator.....	63
4.7.12	EMF Editor Tool.....	65
4.7.12.1	EMF Measurement Set Editor.....	66
4.7.12.2	EMF Measurement Configuration Editor.....	70
4.8	Analyze the Instrument Dataset.....	73
4.8.1	Spectrogram.....	73
4.8.2	Map Analysis.....	77
4.8.3	GPX Conversion.....	79
4.8.4	Dataset Image.....	81
4.8.5	EMF Measurement Result.....	82
4.9	Options.....	88
4.9.1	Color Settings.....	88
4.9.2	Directory Settings.....	90
4.9.3	Application Settings.....	91
4.9.4	Keyboard Shortcuts.....	92
4.9.5	Command-Line Tool.....	92
4.9.6	About.....	93
	Index.....	94

1 Installing R&S InstrumentView

Installing the R&S InstrumentView software


The R&S InstrumentView allows you to remotely control the instrument via LAN or USB interface. It is an application software which provides printing service, customize report generation and editorial functions on the different datasets used in the instrument. The R&S InstrumentView also provides post-processing features to edit the markers position on the trace measurements.

The R&S InstrumentView supports a wide range of spectrum analyzer, i.e. R&S FSH4, R&S FSC, R&S ZVH, R&S FPH, R&S ZPH and R&S FPC.



The setup program installs the R&S InstrumentView software on PC's running Windows 7, 8 and 10.

To install the software, download the latest software installer from the individual spectrum analyzer product homepage, i.e. www.rohde-schwarz.com/product/fph.

Running the R&S InstrumentView software



There are a few ways to start the R&S InstrumentView software:

- Double-click the R&S InstrumentView icon  on the desktop of the PC.
- Navigate to "Start", select "All Programs > Rohde-Schwarz > Instrument View" and click the application icon .

About the software information

To display the software information for R&S InstrumentView, select the "About" menu item in the "Options" menu. See [Figure 1-1](#).




Figure 1-1: About R&S InstrumentView

2 R&S InstrumentView Screen Layout



Context Menu

Right-click on the trace measurement window, horizontal scrollbar or vertical scrollbar to access the following menus:

Trace measurement window

- "Reset Zoom", "Reset Move" - Resets to original zoom level or moved position
- "Copy Graphics" - Copies the selected trace from the trace window to the clipboard
- "Copy Graphic with Label" - Copies the trace window and the "Measurement Setup" details to the clipboard.

This context menu is only available for R&S ZPH product series.

- "Copy Data" - Copies the instrument setup and trace data from the trace window to the clipboard
- "Copy Active Sweep" - Copies the selected trace from the trace window. When a trace is selected, the corresponding grid color on the Y-axis changed accordingly.
- "Paste Sweep" - Trace copied to the clipboard is pasted into the trace window
- "Delete Active Sweep" - Deletes the selected trace from the trace window. When a trace is selected, the corresponding grid color on the Y-axis changed accordingly.
- "View Display Line" - A useful feature to visibly show the display line level
- "View Grid" - Enables or disables the display of grid line on the trace window

Horizontal scrollbar

- "Scroll Here" - Navigates to the cursor position
- "Left Edge", "Right Edge" - Navigates to the extreme left or right of the scrollbar position
- "Page Left", "Page Right" - Pages left or right on the scrollbar position
- "Scroll Left", "Scroll Right" - Navigates left or right on the scrollbar position

Vertical scrollbar

- "Scroll Here" - Navigates to the cursor position
- "Top", "Bottom" - Navigates to the top or bottom of the scrollbar position
- "Page Up", "Page Down" - Pages up or down on the scrollbar position
- "Scroll Up", "Scroll Down" - Navigates up or down on the scrollbar position

The following illustrates the display of the R&S InstrumentView screen layout.












Figure 2-1: R&S InstrumentView screen layout

- 1 = Connection manager menu
- 2 = R&S InstrumentView menu
- 3 = Tab header bar
- 4 = Drop-down box to show hidden tabs in the Tab header bar
- 5 = Displays dialog box associated with the selected tab in the Tab header bar
- 6 = Trace measurement of the selected tab
- 7 = Mouse menu option. See details in Table 4-9.
- 8 = Context menu for trace measurement window
- 9 = Context menu for vertical scrollbar
- 10 = Context menu for horizontal scrollbar

Table 2-1: R&S InstrumentView menu

R&S InstrumentView menu	Function
 Print	Prints and displays the print preview of the trace measurements. See Chapter 4.1, "Printing Trace Windows", on page 15.
 Report Generator	Customizes the report generation for the trace measurement results. See Chapter 4.2, "Report Generator", on page 17.
 Open	Opens an existing trace measurement from the PC. See Chapter 4.4, "Open Instrument", on page 22.
 Save	Saves the trace measurements and dataset. See Chapter 4.3, "Save Instrument", on page 20.
 Get Trace	Retrieves a trace measurement from the connected instrument. See Chapter 4.5.1, "Get Trace", on page 22.
 Add Trace	Adds a trace measurement from the connected instrument to the existing trace measurement. See Chapter 4.5.2, "Add Trace", on page 28.

R&S InstrumentView menu	Function
 Instrument ▶	<p>Remote display and control of the instrument from PC. See Chapter 4.6.1, "Remote Display", on page 30.</p> <p>Provides a snapshot of all connected devices. See Chapter 4.6.2, "Lab Display", on page 34.</p> <p>Files transfer between the instrument and PC. See Chapter 4.6.3, "File Transfer", on page 34.</p> <p>Synchronizing files between instrument and PC. See Chapter 4.6.4, "Synchronization", on page 37.</p> <p>Multiple transfers of trace measurements from the instrument to PC. See Chapter 4.6.5, "Multi-Transfer", on page 39.</p> <p>Captures a screenshot from the instrument. See Chapter 4.6.6, "Screenshot", on page 42</p> <p>Date time synchronization. See Chapter 4.6.7, "Date Time Synchronization", on page 43.</p> <p>Saves current active instrument dataset. See Chapter 4.6.8, "Save Active Dataset", on page 43.</p> <p>Activates dataset from PC to instrument. See Chapter 4.6.9, "Activate Dataset to Instrument", on page 43.</p>
 Preparation ▶	<p>Edits the different datasets supported by the instrument family.</p> <p>See Chapter 4.7, "Working with Instrument Datasets", on page 45.</p>
 Analysis ▶	<p>Provides post data analysis for spectrogram and map analysis.</p> <p>Provides GPX conversion to KMZ and CSV file format.</p> <p>See Chapter 4.7.11, "Map Creator", on page 63.</p>
 Options ▶	<p>Provides color settings on the different elements in trace window.</p> <p>Configures the local directory settings for the different types of files used in the application.</p> <p>Provides setting to enable the retrieve of full dataset from instrument.</p> <p>Displays the keyboard shortcuts key.</p> <p>Displays the application software information.</p> <p>See Chapter 4.9, "Options", on page 88.</p>

Tab header bar

After the PC is successfully connected to the instrument, new tabs appear in the "Tab header bar" when a menu item is selected from the R&S InstrumentView menu.

Tab selected for usage is highlighted with a horizontal blue line in the tab. See an example in [Figure 2-2](#).




Figure 2-2: Selected tab



3 Connecting the Instrument

The InstrumentView software communicates with your instrument via USB or Ethernet (LAN).

You can select the type of connection using the connection manager menu at the top right-hand corner of the screen layout. See [Figure 2-1](#).

The connection manager menu also displays the instrument connection status.

Table 3-1: Connection status

Connection status	Function
 Connected	One or more instruments are connected with the PC
 Not Connected	No instrument is connected with the PC

3.1 Connection Manager Menu




Context Menu

Right-click in the connection manager list to access the following menus:

- "Connection All" - Connects all the listed instruments in the connection manager list
- "Connection Selection" - Connects only the selected instrument in the connection manager list
- "Disconnection All" - Disconnects all the listed instruments in the connection manager list
- "Disconnection Selection" - Disconnects only the selected instrument in the connection manager list

The "Connection Manager" menu configures the remote connection between the PC and the instrument.

Depending on the connection status icon   , you can connect or disconnect the instrument from the connection manager list.






Figure 3-1: Connection manager menu

- 1 = LAN connection tab
- 2 = USB connection tab
- 3 = List of connections tab
- 4 = Connected instrument
- 5 = Connection manager list for LAN connection
- 6 = Selects "Add Devices" button to configure a new instrument
- 7 = Selects "Disconnect" / "Connect" button to connect or disconnect instruments from the connection manager list
- 8 = Selects "Done" button to exit the "Connection Manager" dialog box

LAN connection

1. During the initial startup, the "IP-Address" field is set to default "172.17.75.1". The IP address can be edited using the icon .
2. Select the "Add Devices" button to add a new instrument for LAN connection, s
3. Using the  icon, you can check the available network adapter connected on the PC.

- Once the list is set up with a desired "Name" and "IP address", selects "OK" button to add the new instrument to the connection manager list.

The screenshot shows a dialog box titled "Add Single Device". It contains two main sections. The first section, "Add Single Device", has a "Name" field with the text "Demo" and an "IP Address" field with the text "172.25.56.61". To the right of the IP field is a "Default" button. The second section, "Discover Network Devices", features a "Network Adapter" dropdown menu. The dropdown is open, showing a list of network connections: "Local Area Connection", "Wireless Network Connection 2", "Bluetooth Network Connection", "Wireless Network Connection" (which is highlighted in blue), "Local Area Connection", and "VirtualBox Host-Only Network". To the right of the dropdown is a search icon. At the bottom of the dialog are "Ok" and "Cancel" buttons.


Figure 3-2: Device connection information

USB connection

When the instrument is connected to the PC for the first time, Windows tries to install the new hardware automatically. The required drivers are installed along with the R&S InstrumentView software package.

When the drivers have been found on your system and the hardware has been successfully installed, Windows shows a corresponding message.

There is only one USB instance in the connection manager list. See [Figure 3-3](#).

Depending on the connection status icon  , you can connect or disconnect an instrument from the connection manager list.






Figure 3-3: USB connection



List of connections



Only one USB connection instance is supported at any time.

To view a list of instruments connected to the PC, select the "Connections" tab on the "Connection Manager" dialog box.

The connection status is displayed accordingly to the type of connection established between the PC and instrument, e.g. USB , LAN .

Depending on the connection status icon  , you can connect or disconnect an instrument from the connection manager list.




Figure 3-4: List of connected devices

4 Using R&S InstrumentView

The following chapters illustrate the functionality of the R&S InstrumentView in details.

4.1 Printing Trace Windows



Context Menu

Right-click in the print preview window to access the following menus:

- "Increase Zoom" - Zoom-in on the print preview details
 - "Decrease Zoom" - Zoom-out on the print preview details
-



Dual Trace

The dual trace feature is supported in the R&S ZPH product series only.

Each trace contains its own marker set values.



The "Print" menu allows you to print the trace measurements currently loaded in the R&S InstrumentView. It also displays the print preview window on the printed output.

Arrangement of the printing sequence is possible by dragging the trace measurement window in the "Selection" section. See [Figure 4-1](#).




Figure 4-1: Print dialog

1 = Arrangement of the number of trace measurement windows per page (1, 2, 4, 6, 16 per page)

2 = [Print preview tool](#)









3 = Orientation on the printed output

4 = Preview window

5 = "Color mode" defines the window background color as black or white

6 = "Selection" displays the printed order of the trace measurement windows

Table 4-1: Print preview tools

Print preview tools	Function
Print or (Ctrl+P) 	Prints the preview output.
Copy (Ctrl+C) 	This action is not available.
Zoom in (Ctrl+) 	Zoom-in the preview details.
Zoom out (Ctrl-) 	Zoom-out the preview details.
100% (Ctrl+1) 	Previews the actual print size of the trace measurement window.
Page width (Ctrl+2) 	Previews the whole width size of the trace measurement window.
Whole page (Ctrl+3) 	Previews a single page of the trace measurement result in the preview window.
Two pages (Ctrl+4) 	Previews two pages of trace measurement results on the same row in the preview window.

4.2 Report Generator



The "Report Generator" menu allows you to select logo, report output format and language and selectively display measurements parameters to customize the test report. See [Figure 4-2](#).









Figure 4-2: Report generation dialog

- 1 = Displays report library directory path
- 2 = Selects "Refresh" button to refresh the files in the selected report library directory
- 3 = [Homepage](#)
- 4 = Opens the PC window explorer to set report library directory path
- 5 = List of dataset files extracted from the report library directory. See [Chapter 4.3, "Save Instrument"](#), on page 20
- 6 = [Dataset/Screenshot tools](#)
- 7 = List of dataset sequence to be generated in report
- 8 = [Report parameters](#)
- 9 = User customization for logo and report language and format (PDF, HTML, RTF)
- 10 = Activates "Open after Generation" checkbox to open the file after report generation
- 11 = Selects "Preview" button to preview the report format
- 12 = Activates "Generate" button to generate the report
- 13 = "Measurement Settings" to insert additional comment and screenshots at the end of the report

Table 4-2: Dataset/Screenshot tools

Report tools	Function
"View" 	Views dataset/screenshot.
"Add" 	Adds selected dataset/screenshot.
"Remove" 	Deletes the selected dataset/screenshot.

Report tools	Function
"Up" 	Moves forward the selected dataset/screenshot.sequence.
"Down" 	Moves backward the selected dataset/screenshot.sequence.

Report parameters


The following shows a snapshot of the report generated. See [Figure 4-3](#).

It shows the details parameters in the "General Information", "Measurement Results" and "Measurement Settings" section. These details parameters are configurable for report generation. See index 8 of [Figure 4-2](#).

Date: 10/5/2018	Instrument: ZPH - 999991/002
User:	Site:
Comments:	

Measurement Results

DTF



Markers			
M 1 Position	19.68 m	M 2 Value	-46.81 dB
M 1 Value	-45.20 dB	M 3 Position	27.68 m
M 2 Position	50 m	M 3 Value	-47.56 dB

Limit Line Results	
Threshold (Upper)	-36.00 dB PASS

Measurement Setup			
Date	10/5/2018	Start Distance	9.000 m
Time	10:32:10 AM	Stop Distance	50.000 m
Instrument	ZPH - 999991/002	Start Frequency	1.270390417 GHz
Meas Mode	DTF	Stop Frequency	1.731609583 GHz
Calibration State	Default Calibration	Cable Model	<none>
Trace 1 Setup			
Trace Mode	Clear / Write	Format	Magnitude
Range	50 dB	Ref Level	-12 dB

Figure 4-3: Test report generated

- 1 = General Information
- 2 = Marker data
- 3 = Measurement results
- 4 = Measurement settings

4.3 Save Instrument



Depending on the types of dataset or trace windows (e.g. screenshot) that the R&S InstrumentView is working with, the "Save" function saves the files in their respective file format. See [Table 4-3](#).

Table 4-3: File format

Description	File format
Primary transducer factor, secondary transducer factor and isotropic transducer factor See Chapter 4.7.1, "Using Transducers" , on page 45.	*.pritrd, *.sectrd, *.isotrd
Cable models See Chapter 4.7.2, "Using Cable Models" , on page 47.	*.cblmod
Calibration kit See Chapter 4.7.3, "Calibration Kits" , on page 48.	*.ckit
Relative limit line and absolute limit line See Chapter 4.7.4, "Using Limit Lines" , on page 49.	*.relli, *.absli
Channel table See Chapter 4.7.5, "Using Channel Table" , on page 51.	*.chnta
Standards table See Chapter 4.7.6, "Using Standards" , on page 52.	*.semst, *.chpst, *.obwst, *.tdmst
Quick name table See Chapter 4.7.7, "Using Quick Name Table" , on page 56.	*.qnt
Ama limits See Chapter 4.7.8, "Using Analog Modulation Analysis AM Limits" , on page 57 and Chapter 4.7.9, "Using Analog Modulation Analysis FM Limits" , on page 58.	*.aamlim, *.fmlim
Datasets See Chapter 4.6.8, "Save Active Dataset" , on page 43 and Chapter 4.6.9, "Activate Dataset to Instrument" , on page 43.	*.set, *xset, *cset,
EMF See Chapter 4.7.12.1, "EMF Measurement Set Editor" , on page 66 and Chapter 4.7.12.2, "EMF Measurement Configuration Editor" , on page 70. See also Chapter 4.8.5, "EMF Measurement Result" , on page 82.	*.emcf, *.emrf, *.emdf
Screenshot. See Chapter 4.6.6, "Screenshot" , on page 42.	*.png, *.bmp, jpg, *.gif
Trace measurement with setup configuration details See Chapter 4.5, "Working with Trace Windows" , on page 22.	*.set
Measurement wizard set See Chapter 4.7.10, "Wizard Set Editor" , on page 58	*.mdf, xmdf

Description	File format
Map data See Chapter 4.7.11, "Map Creator" , on page 63.	*.idm, *.prj, *.gpx
Spectrogram See Chapter 4.8.1, "Spectrogram" , on page 73.	*.spm
CSV instrument file reconstruction supports Transducer , Cable Model , Channel Table , Limit Line , AMA AM Limit , AMA FM Limit and Standard	*.csv

4.4 Open Instrument



Context Menu

See details of the context menu in [Chapter 2, "R&S InstrumentView Screen Layout"](#), on page 7.



The "Open" menu allows you to open the existing trace measurements or datasets from the PC and displayed it in the trace window. A new tab is formed in the "Tab header bar" for each trace measurement or dataset opened from the PC.

For trace measurement, see details in [Figure 4-4](#).

For dataset supported, see details in [Chapter 4.7, "Working with Instrument Datasets"](#), on page 45.

4.5 Working with Trace Windows

The following illustrates the ways how you can work with the trace measurements in R&S InstrumentView.

- [Get Trace](#)..... 22
- [Add Trace](#)..... 28

4.5.1 Get Trace



Context Menu

See more details of the context menu in [Chapter 2, "R&S InstrumentView Screen Layout"](#), on page 7.



The "Get Trace" menu allows you to capture the current trace measurement from the instrument and display it in the trace window. A new tab is formed in the "Tab header bar" for every new trace captured from the instrument. See index 1 in [Figure 4-4](#).

Each trace measurement result consists of two tabs:

- "Measurement"
 - "Measurement Setup"
Details of the instrument measurement settings. See user manual of the respective instrument for details of measurement settings.
 - "Measurement Results" (if any)
Pass/Fail result of the limit test.
See index 6 and 7 in [Figure 4-4](#).
 - "Markers" (if any)
Setting of the markers position.
- "Setup"
Trace measurement details captured from the instrument are displayed in the "Setup" tab. You can edit existing setup information or add additional setup information on the selected trace measurement. See index 3 in [Figure 4-4](#).

The screenshot displays the R&S InstrumentView interface for a trace measurement. The main window shows a plot of signal magnitude (dB) versus distance (m). The plot includes a yellow trace, two horizontal limit lines (one at -28.5 dB and one at -45.5 dB), and several markers. The 'Measurement' and 'Setup' tabs are active. The 'Trace Setup' panel is expanded, showing 'Trace Settings' and 'Limit Line Settings'. The 'Marker Setup' panel is also expanded, showing 'Marker Position' settings for six markers. The 'Copy Labels Setup' panel is expanded, showing a list of data fields to be copied.

Figure 4-4: Trace measurement window

- 1 = Tab header bar
- 2 = "Measurement" tab
- 3 = "Setup" tab
- 4 = Marker position
- 5 = Delta marker position
- 6 = Upper limit of limit line 1
- 7 = Trace shows that result failed at limit line 1
- 8 = Lower limit of limit line 2

- 9 = [Trace Setup](#)
- 10 = [Marker Setup](#)
- 11 = [Copy Label Setup](#)

Trace Setup

The "Trace Setup" dialog is divided into three different settings: trace setup, memory trace and limit line settings.

- Each trace is represented with a different trace color. If there is more than one trace in the same trace window, you can go to the individual trace tab to disable or enable the "Show Trace" checkbox to set the trace display. See [Figure 4-5](#). The following "Trace Unit" and "Trace Range" are selectable:
 - "Trace Unit"
"dBm", "dBmV", "dμV", "V", "W"
 - "Trace Range"
"150 dB (15.0 dB/Div)", "130 dB (13.0 dB/Div)", "120 dB (12.0 dB/Div)", "100 dB (10.0 dB/Div)", "50 dB (5.0 dB/Div)", "30 dB (3.0 dB/Div)", "20 dB (2.0 dB/Div)", "10 dB (1.0 dB/Div)", "5 dB (0.5 dB/Div)", "3 dB (0.3 dB/Div)", "2 dB (0.2 dB/Div)", "1 dB (0.1 dB/Div)", "Linear 0-100%"
- The "Show Memory Trace" is only enabled if the trace measurement captured from the instrument contains the memory trace information. With the memory trace, you can apply "Trace Math" method ("Trace - Memory", "Memory - Trace") between the trace and memory and see the result on the trace window. The "Math Position" shifts the trace resulted from "Trace Math" to the position defined in the entry box. For more information on the memory trace, see the respective instrument user manual.
- The "Limit Line Settings" provides two sets of limit line that you can apply on the trace window. Each set of the limit line provides the selection to apply it as "Upper Limit" or "Lower Limit". The test result of the limit line is displayed in the "Measurement" tab. See index 2 in [Figure 4-4](#). Selects "Select" to select the desired limit line from the "Limit Lines" folder directory in the PC. See [Chapter 4.9.2, "Directory Settings"](#), on page 90. You can enable or disable the display of the limit line using the "Show Limit Line 1" or "Show Limit Line 2" checkbox.




Figure 4-5: Trace setup

Marker Setup

The "Marker Setup" allows you to label the trace measurement with up to six different markers. For more information on marker details, see the respective instrument user manual.

The first marker is always set as "M1" with the rest labeled as marker (M2, M3, M4, M5, M6) or delta marker (D2, D3, D4, D5, D6). See [Figure 4-6](#).

The marker value can be individually positioned in the following ways:

- Value (Hz)
Key in the desired frequency value in the entry box.
- "To Peak", "To Next Peak", "To Minimum"
Auto-positioning of the marker value by selecting the peak, next peak or minimum value across the span width of the trace measurement.
- Auto positioning of marker value ("To Peak", "To Next Peak", "To Minimum") in the area defined by the search limit ("Search Limit 1" or "Search Limit 2").
The "Start Search 1", "Start Search 2", "Stop Search 1" and "Stop Search 2" defined the search start and stop limit.
You can also find the auto positioning of the marker value using the "N dB (M1)".
This search function is only restricted to "M1" and available in spectrum operating mode.
- "All Markers"
This section is used to synchronize the criteria of all the marker positions.

▼ Marker Setup

	Off	Marker	Delta Marker	Value (Hz)	To Peak	To Next Peak	To Minimum	Search Limit Off	Search Limit 1	Search Limit 2
Marker 1 (M1)	<input type="radio"/>	<input checked="" type="radio"/>	<input type="radio"/>	0	<input type="button" value="↙"/>	<input type="button" value="↘"/>	<input type="button" value="⏴"/>	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>
Marker 2 (D2)	<input type="radio"/>	<input type="radio"/>	<input checked="" type="radio"/>	116160563.380282	<input type="button" value="↙"/>	<input type="button" value="↘"/>	<input type="button" value="⏴"/>	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>
Marker 3 (M3)	<input type="radio"/>	<input checked="" type="radio"/>	<input type="radio"/>	82007042.2535211	<input type="button" value="↙"/>	<input type="button" value="↘"/>	<input type="button" value="⏴"/>	<input type="radio"/>	<input checked="" type="radio"/>	<input type="radio"/>
Marker 4	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>	2000000000	<input type="button" value="↙"/>	<input type="button" value="↘"/>	<input type="button" value="⏴"/>	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>
Marker 5	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>	2000000000	<input type="button" value="↙"/>	<input type="button" value="↘"/>	<input type="button" value="⏴"/>	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>
Marker 6	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>	2000000000	<input type="button" value="↙"/>	<input type="button" value="↘"/>	<input type="button" value="⏴"/>	<input type="radio"/>	<input type="radio"/>	<input type="radio"/>
All Markers	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>		<input type="button" value="↙"/>			<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Start Search 1	<input type="text" value="70"/>	MHz	Stop Search 1	<input type="text" value="90"/>	MHz					
Start Search 2	<input type="text" value="0"/>	MHz	Stop Search 2	<input type="text" value="4000"/>	MHz					
N dB (M1)	<input type="checkbox"/>	<input type="text" value="3"/>	dB							

Figure 4-6: Marker setup

Copy Label Setup



"Copy Label Setup" is only available with R&S ZPH product series.

The "Copy Label Setup" allows you to check or uncheck the measurement fields that are copied when using the context menu "Copy Graphic with Label". See "[Context Menu](#)" on page 22.




Figure 4-7: Copy Labels Setup dialog

4.5.2 Add Trace




The "Add Trace" is not applicable for R&S ZPH product series.



Context Menu

See more details of the context menu in [Chapter 2, "R&S InstrumentView Screen Layout"](#), on page 7.



The "Add Trace" menu allows you to add additional trace measurement captured from the instrument to an existing trace measurement displayed in the trace window. Each trace is represented with a different trace color. See [Figure 4-8](#).

See details of "Measurement" tab in index 2 of [Figure 4-4](#).

See details of "Setup" tab in index 3 of [Figure 4-4](#).




Figure 4-8: Add a trace to an existing trace measurement

4.6 Working with Instrument



The "Instrument" menu provides the following functions:




- Remote display and control of the instrument
- Snapshot display of all connected instrument
- Files transfer between instrument and PC
- File synchronization between instrument and PC
- Multiple updates of screenshot from instrument to PC
- Screenshot captured from the instrument
- Date and time synchronization between instrument and PC
- Saves a dataset from the instrument to PC
- Activates a dataset from PC to instrument
- Firmware update

- [Remote Display](#).....30
- [Lab Display](#).....34
- [File Transfer](#).....34
- [Synchronization](#).....37
- [Multi-Transfer](#).....39
- [Screenshot](#).....42
- [Date Time Synchronization](#).....43

- [Save Active Dataset](#).....43
- [Activate Dataset to Instrument](#).....43
- [Firmware Update](#).....44

4.6.1 Remote Display

**To enter value:**

- Select the left side of the rotary knob  to decrease entry value and right side of the rotary knob  to increase entry value.
 - Select the center of the rotary knob  to confirm the entry value
-

The "Remote Display" provides the remote display and control of the instrument. You can remotely control and display the instrument via the softkey and hardkey function displayed. See [Figure 4-9](#).

See the respective instrument user manual for details of each of the softkey and hardkey functions.





Figure 4-9: Remote display of the instrument

4.6.1.1 Remote Display with Troubleshooting

When establishing a remote connection with the instrument, a message "Establishing Remote Connection..." is displayed. When there is a connection failure, the "Connection Error" popup message is displayed. The timeout for connection error is 30 seconds.




There are two possibilities for a connection failure:

USB device not initialized


The virtual network adapter for the USB device has not yet initialized after plugging in the USB cable. This process takes at least 10 seconds and it varies per PC setup.

You can view the status of the USB device under Control Panel\Network and Internet\Network Connections settings in the PC operating system.

- USB device not ready




- USB device ready




RNDIS drivers not properly installed

You can verify the RNDIS drivers status in two ways:

- Under Control Panel\Programs\Programs and Features settings: The R&S InstrumentView RNDIS Driver (32-Bit or 64-bit) and Windows Driver Package - Rohde & Schwarz ESNA installments must be present.



- Under Control Panel\System and Security\System -> Device Manager settings: For FPH/ZPH/FPC, it should contain the following three devices:
 - USB Composite Device *with VID_0AAD*
 - USB Test and Measurement Device (IVI) *with VID_0AAD*
 - Network adapter with the name Rohde & Schwarz <device type> Instrument. The highlighted "Rohde & Schwarz ZPH Instrument" network adapter would not show up in case the RNDIS driver is not correctly installed on the PC.



If connection failure still persists, it is recommended to uninstall and reinstall the R&S InstrumentView software package. See [Chapter 1, "Installing R&S InstrumentView"](#), on page 5.

4.6.2 Lab Display



Context Menu

Right-click on the instrument snapshot for the following menus:

- "Recall file on this device"
This function recalls a dataset stored on the PC to the selected device.
- "Copy setup"
This function copies the measurement setup of the selected device to the internal clipboard of R&S InstrumentView.
- "Paste setup"
This function pastes the measurement setup from the internal clipboard of R&S InstrumentView to the selected device
- [Remote display](#)
- "Recall all from this device"
This function retrieves the measurement setup of the selected device and recalls it on all currently connected devices in the display window.
- "Recall all from file"
This function recalls a dataset stored on the PC to the all connected devices in the display window.

The "Lab" menu displays a snapshot of all the connected instruments in the display window.

Each snapshot provides you an instrument identity and overview of the current measurement:




Figure 4-10: Snapshot of all connected instruments

4.6.3 File Transfer

The "File Transfer" provides the file transfer between the instrument and PC. You can make single or multiple files transfer or perform a file synchronization between the instrument and PC. See [Figure 4-11](#).










Figure 4-11: File transfer dialog

- 1 = Instrument icon.
- 2 = PC icon.
- 3 = [Homepage](#)
- 4 = File transfers from the instrument to PC and vice versa
- 5 = Instrument's folder directories
- 6 = PC's folder directories
- 7 = [File transfer tools](#)
- 8 = [Templates & result synchronization](#)
- 9 = List of selected files from the instrument

- 10 = List of selected files from the PC
 11 = Progress bar showing the current folder synchronizing between the instrument and PC
 12 = Progress bar showing the current file synchronizing between the instrument and PC
 13 = Progress update dialog for "Templates and Results" synchronizing

Table 4-4: File transfer tools

Icon	Function
"Delete" 	Deletes the selected file.
"Lock" 	Locks or unlocks the selected file. Alternative, you can select the  icon to unlock or lock the file. Note: A locked file is a read-only file, it can only be viewed and transferred.
"Refresh" 	Refreshes the file content in the selected folder directory.
"Search" 	Performs a file search function in the selected folder directory.
"View" 	Views the details of the trace measurement file. For viewing, see Chapter 4.3, "Save Instrument" , on page 20 for a list of file format supported. When a file is selected to be viewed, a tab is displayed in the header bar of the screen layout. See index 11 of Figure 4-13 .

Homepage

When activated, the homepage helps you to set the directory path back to the root directory.

- `\Public` for instrument
- `..\Users\Public\Documents\Rohde-Schwarz\InstrumentView` for PC

See [Chapter 4.9.2, "Directory Settings"](#), on page 90.

Templates & result synchronization

The "Templates & Result" synchronizes the different datasets and screenshots between the instrument and PC.

When activated, the file synchronization dialog box is displayed. It shows the progress status of the current folder and filename being synchronized. See index 13 in [Figure 4-11](#).

When a file transfer conflict is detected during the synchronization process, the conflict dialog box is displayed to resolve the conflict. See [Figure 4-12](#)




Figure 4-12: Conflict dialog box

1. Select "Overwrite older files" to overwrite older file with the newer file.
2. Select "Do this for all conflicts" to perform the "Skip" or "Overwrite" function in the current folder.

4.6.4 Synchronization



Context Menu

Right-click on the synchronization dialog box to access the following menus:

Synchronization dialog box

- "Include All", "Exclude All" - Includes or excludes all the directories for file transfer.
- "Move Up", "Move Down" - Navigates the directories list.

Vertical scrollbar


- See details in ["Context Menu"](#) on page 7.

Horizontal scrollbar

- See details in ["Context Menu"](#) on page 7.

The "Synchronization" menu allows you to synchronize files between the local PC to instrument, vice versa.

You can use the overwriting option to decide how you want to synchronize the files when there is a conflict of files transfer.



- 1 = Checkbox to select file directories for transfer
- 2 = Instrument file directories
- 3 = Direction of files transfer
- 4 = PC file directories
- 5 = Scrollbar to navigate files directories window
- 6 = File transfer icon to active file transfer from PC to instrument
- 7 = File synchronization icon to active file synchronization between PC and instrument, vice versa
- 8 = File transfer icon to activate file transfer from instrument to PC
- 9 = Overwriting option dialog box
- 10 = [File manger icons](#)

Table 4-5: File manager icons

File manager icon	Function
Default	Presets the file directories window to default configuration
Add	Adds a new file directory to the file directories window
Delete	Deletes a new file directory to the file directories window
Remote	Accesses instrument file directories
Local	Accesses to local home directory

4.6.5 Multi-Transfer

The "Multi Transfer" menu allows you to capture and save trace measurements from the instrument. See [Figure 4-13](#).




Figure 4-13: Multi-transfer dialog

- 1 = "Multi Transfer" tab displays the "Multi Transfer" dialog for settings
- 2 = Measurement results tab (see index 11 in [Figure 4-13](#))
- 3 = Drop-down icon to display the tab hidden in the "Tab header bar" (see index 4 in [Figure 2-1](#))
- 4 = [Number of updates](#)
- 5 = Display settings to configure the display of [results](#) for the trace measurement
- 6 = [Auto save](#) settings for the auto save function
- 7 = "Start/Stop icon" on page 41 to record or stop the trace measurements captured from instrument
- 8 = Overview display area for trace measurement captured from the instrument
- 9 = File browser to show that trace measurement files are captured with a prefix "MT20151028" defined in "Session name"
- 10 = Details of the hidden tab displayed from the drop-down icon
- 11 = Details of the selected trace measurement in the "Tab header bar"

Number of updates

The trace measurement can be updated with the following conditions:

- Single sweep with a fixed number.
Default value is 5. Maximum value is 100000.
- Continuous sweep

The trace measurement is captured with a fixed interval timing defined by "Interval".
Default value is 10. Maximum value is 3600.

Results

There are two ways to display the trace measurements captured from the instrument.

- The trace measurement in the overview area. See index 8 in [Figure 4-13](#).
 - The individual trace measurement result in the "Tab header bar". See index 2 in [Figure 4-13](#).
- ▶ Select the individual trace measurement captured in the overview area to display the details information of trace measurement in the "Tab header bar".

See index 11 in [Figure 4-13](#).

See also [Chapter 4.5.1, "Get Trace"](#), on page 22.

Auto save

The "AutoSave" performs an auto save function on the trace measurement updates from the instrument to PC hard disk.

The trace measurements are saved with a prefixed filename configure in the "Section name" and with an incremental order from "_000001" to "_xxxxxx". The "Save in" defined the file directory where these trace measurements are saved.

See index 9 in [Figure 4-13](#) to view the trace measurements captured in the file directory.

Start/Stop icon



The R&S InstrumentView prompts you to save unsaved data captured in the last recording session when the "Start" function is activated. See [Figure 4-14](#).






Figure 4-14: Unsaved data user prompt dialog box

The "Start" icon  performs the recording function to capture the trace measurement updates from the instrument.

Depending on the setting in the "Results" section (see index 5 in [Figure 4-13](#)), the trace measurement updates can be displayed in the overview area (see index 8 in [Figure 4-13](#)) or individually displayed as a new tab in the tab header bar (see index 2 in [Figure 4-13](#)).

When the "Start" is activated, the "Start" icon  changes to "Stop" icon . The "Stop" icon allows you to stop the recording process. When the "Stop" is activated, the R&S InstrumentView opens the "Delete" dialog. See [Figure 4-15](#).




Figure 4-15: Delete dialog

- ▶ Select "Yes" to stop the recording process.

4.6.6 Screenshot



Context Menu

Right-click on the trace window to access the following menus:

- "Show measurement setup" - If enabled, the instrument settings and the trace data are displayed below the screenshot. See [Figure 4-16](#).
- "Copy to clipboard" - Copies the screenshot to the clipboard.

The "Screenshot" is used to capture the active instrument screen and display it in the trace window. See [Figure 4-16](#).

This trace window is printed or saved for further editing in the application.




Figure 4-16: Screenshot

4.6.7 Date Time Synchronization

The "Date Time Sync" is used to synchronize the date and time of the connected instrument with PC.

- ▶ Select "OK" to confirm the "Date and Time" synchronization. See [Figure 4-17](#).





Figure 4-17: Date and time synchronization

4.6.8 Save Active Dataset

The "Active to Dataset" is used to save the current active dataset from the instrument to PC.

- ▶ Select "Active to Dataset" to browse to the local PC directories to save the dataset file.
A message is displayed when the dataset file is saved successfully.




4.6.9 Activate Dataset to Instrument

The "Dataset to Active" menu is used to activate a dataset file from PC to the instrument.

To view dataset image, see [Chapter 4.8.4, "Dataset Image"](#), on page 81.

- ▶ Select "Dataset to Active" to browse a dataset file from the local PC directories and activate it to the instrument.
A message is displayed when the dataset file is activated successfully.



4.6.10 Firmware Update



Instrument selected for firmware update must be powered by a power adapter. USB or SD card storage is needed in each device during the firmware update.

The "Firmware Update" menu provides the firmware update for the range of instruments supported by R&S InstrumentView.

Firmware update can be performed concurrently on the selected instruments belonging to the same instrument family.




Figure 4-18: Firmware update dialog

- 1 = Settings for the firmware update
- 2 = Status of the firmware update process
- 3 = Instrument family selection (FPH, ZPH, FPC, FSC, FSH4, ZVH4)
- 4 = Instrument list
- 5 = File browser to display the file folders
- 6 = Displays the [Connection Manager](#)
- 7 = Displays file browser to search instrument firmware

4.7 Working with Instrument Datasets

Preparation ▾

The "Preparation" menu allows you to configure the different dataset used in the instrument. See the following sections for more information on the dataset editor.

• Using Transducers	45
• Using Cable Models	47
• Calibration Kits	48
• Using Limit Lines	49
• Using Channel Table	51
• Using Standards	52
• Using Quick Name Table	56
• Using Analog Modulation Analysis AM Limits	57
• Using Analog Modulation Analysis FM Limits	58
• Wizard Set Editor	58
• Map Creator	63
• EMF Editor Tool	65

4.7.1 Using Transducers

The frequency-dependent transducers table is used to correct the level values of the trace measurement for frequency-dependent components such as antennas, splitters and cables used in the test measurements.

The R&S InstrumentView comes with a list of predefined transducers tables for R&S components such as antennas and matching pad. Using the "Transducers" editor menu, you can customize the transducers table used for the frequency-dependent components introduced in your test measurements. See "[Transducers table editor](#)" on page 45.

Each transducer table may consist of up to 1000 reference values.

Transducers table editor

The "Transducers" table editor allows you to open, edit and save the transducers table. See [Figure 4-19](#).

The screenshot shows the 'Transducer table editor' interface. On the left, there are four input fields: 'Name' (HE200P-HF), 'Description' (HE200 passive 9kHz - 30MHz), 'Unit' (dBµV/m), and 'Type' (Primary). Below these are three buttons: 'New', 'Open', and 'Save'. On the right, there are two tabs: 'Data' and 'Preview'. The 'Data' tab is active, displaying a table with two columns: 'Frequency (Hz)' and 'TRD (dBµV/m)'. The table contains 19 rows of data. A scroll bar is visible on the right side of the table. At the bottom right, there is a 'Sort' button.

	Frequency (Hz)	TRD (dBµV/m)
1	9000	88.7
2	10000	88.7
3	12000	88.4
4	14000	88.1
5	16000	87.7
6	18000	87.1
7	20000	86.5
8	22000	86.1
9	24000	85.7
10	26000	85.4
11	28000	85.1
12	30000	84.7
13	32000	84.4
14	34000	84.1
15	36000	83.8
16	38000	83.5
17	40000	83.2
18	42000	82.8
19	44000	82.5

Figure 4-19: Transducer table editor

- 1 = Name of the transducers table
- 2 = Description of the transducers table
- 3 = "Unit" defines the level unit used in the transducers table ("dBµV/m", "dBµA/m")
- 4 = "Type" defines the type of transducer factor ("Primary", "Secondary", "Isotopic") used for the transducer table
- 5 = "Data" tab shows the details of the transducers table
- 6 = "Preview" tab displays the transducers table in a chart (see ["Preview transducer table"](#) on page 46)
- 7 = Editor of the transducers table
- 8 = Scroll bar
- 9 = "New" button creates a transducer table for entry
- 10 = "Open" button loads an existing transducers table
- 11 = "Save" button saves the current transducers table
- 12 = "Sort" button sorts the "Frequency (Hz)" of the transducers table in ascending order

Preview transducer table

The "Preview" tab displays the transducer table in a chart. It provides an overview of the frequency response of transducer table. See [Figure 4-20](#).




Figure 4-20: Preview transducer table

4.7.2 Using Cable Models



Cable model is only applicable for R&S ZPH, R&S FSC, R&S FSH4 and R&S ZVH product series.

The R&S InstrumentView comes with a list of channel models which describes the cable characteristics. Using the "Cable Models" editor menu, you can customize the cable model according to your requirements.

Cable models editor

The "Channel Models" editor allows you to open, edit and save the cable model. See [Figure 4-21](#).




Figure 4-21: Cable models editor

- 1 = Name of the cable model
- 2 = Description of the cable model
- 3 = Propagation velocity of the cable model
- 4 = Cable frequency
- 5 = Cable attenuation
- 6 = Scroll bar to navigate the cable model editor
- 7 = "New" button creates a cable model for entry
- 8 = "Open" button loads an existing cable model
- 9 = "Save" button saves the current cable model
- 10 = "Sort" button sorts the "Frequency (Hz)" of the cable model in ascending order

Propagation velocity

You can customize the propagation velocity for the cable model or use the following preset configuration:

Type	Absolute m/s	Relative %	Rel. dielectric constant
Solid polyethelene	197700000	65.9	2.3
Foam polyethelene	240000000	80.1	1.56
Foam polystyrene	273000000	91.1	1.21
Solid teflon	208200000	69.4	2.07

4.7.3 Calibration Kits



The "Calibration Kits" editor is only applicable for R&S ZPH, R&S FSH4 and R&S ZVH product series.

The "Calibration Kits" editor provides the necessary parameters for you to define the calibration kit file associated with the calibration kit.

- 1 = Name and description of the calibration kit
- 2 = Parameters for "Open" standard
- 3 = Parameters for "Short" standard
- 4 = Parameters for "Through" standard
- 5 = "New" button creates a calibration kit file for entry
- 6 = "Open" button loads an existing calibration kit file for modification
- 7 = "Save" button saves the current calibration kit file

4.7.4 Using Limit Lines

The limit line is used to identify if a signal complies with a certain level of characteristics. It is made up of two or more points that are connected to a line and each of the point that defines the shape of the limit line consist of two coordinates. One coordinate defines the absolute or relative value of the X-Unit position ("Hz", "s", "m") and the other coordinate is the Y-Unit position ("dB", "dBm", "dBμV", "dBmV", "dBμA/m", "V", "V/m", "W", "W/m²", "VSWR"). See "[Limit lines table editor](#)" on page 49.

The R&S InstrumentView comes with a list of limit lines table which is according to the test transmission standards. Using the "Limit Line" editor menu, you can customize the limit lines table which is deviated from the test transmission standards. See "[Limit lines table editor](#)" on page 49.

Limit lines table editor

The "Limit Line" table editor allows you to open, edit and save the limit lines table. See [Figure 4-22](#).




Figure 4-22: Limit lines table editor

- 1 = Name of the limit lines table
- 2 = Description of the limit lines table
- 3 = "X-Unit" defines the unit used on the x axis of the limit lines table
- 4 = "Y-Unit" defines the unit used on the y axis of the limit lines table
- 5 = "Data" tab shows the details of the limit lines table
- 6 = "Preview" tab displays the limit lines in a chart (see ["Preview limit lines table"](#) on page 50)
- 7 = Editor of the limit lines table
- 8 = Scroll bar
- 9 = "New" button creates a limit line table for entry
- 10 = "Open" button loads an existing limit lines table
- 11 = "Save" button saves the current limit lines table
- 12 = "Sort" button sorts the x axis of the limit lines table in ascending order

Preview limit lines table

The "Preview" tab displays the limit lines in a chart. It provides an overview of the frequency response of the limit lines. See [Figure 4-23](#).




Figure 4-23: Preview limit lines

4.7.5 Using Channel Table

The R&S InstrumentView comes with a list of channel tables which are according to the test transmission standards. Using the "Channel Table" editor menu, you can customize the channel table which is deviated from the test transmission standards. See ["Channel table editor"](#) on page 51.

Channel table editor

The "Channel Table" editor allows you to open, edit and save the channel table. See [Figure 4-24](#).




Figure 4-24: Channel table editor

- 1 = Name of the channel table
- 2 = Description of the channel table
- 3 = Band name in the channel table
- 4 = Starting channel number in the frequency band
- 5 = Starting frequency of the "1st Ch" channel
- 6 = Number of channels in the frequency band
- 7 = Channel spacing between two channels
- 8 = Editor of the channel table
- 9 = "New" button creates a channel table for entry
- 10 = "Open" button loads an existing channel table
- 11 = "Save" button saves the current channel table
- 12 = "Sort" button sorts the "1st Ch" of the channel table in ascending order

4.7.6 Using Standards



The "Standards" table editor is only applicable for R&S FPH, R&S FSC, R&S FSH4 and R&S ZVH product series.

The R&S InstrumentView comes with a list of mobile radio standards with predefined test measurement settings according to the standard's requirements. Using the "Standards" editor menu, you can customize the test measurement settings which are deviated from the standards. See [Chapter 4.7.6.1, "Standards Table Editor"](#), on page 53.

4.7.6.1 Standards Table Editor

The "Standards" table editor allows you to open, edit and save the measurement settings for a test standard. See [Figure 4-25](#).

See the respective instrument user manual for details of each of the measurement settings in the dialog.

Figure 4-25: Standard table editor

- 1 = Name of the standard table
- 2 = Description of the standard table
- 3 = [Measurement Type](#) ("Channel Power", "Occupied Bandwidth", "TDMA", "Spectrum Emission Mask")
- 4 = Details of the "Settings" tab are associated with the "Measurement Type" selected (see [Chapter 4.7.6.2, "Measurement Type"](#), on page 53)
- 5 = Details of the "Channel Power Adjacent Settings" tab are associated with the [Measurement Type](#) selected
- 8 = "New" button creates a new standard table for entry
- 9 = "Open" button loads an existing standard table
- 10 = "Save" button saves the current standard table

4.7.6.2 Measurement Type

Depending on the mobile radio standard used in the test measurements, there are four different types of "Measurement Type" which you can select to customize your measurement settings.

See the respective instrument user manual for details of each of the measurement type.

Channel power

The channel power measurement selectively measures the power of a specified transmission channel and adjacent channels. The following dialog provides the required measurement settings in the "Settings" tab and the TX channels and adjacent channels configuration in the "Channel Power Adjacent Settings" tab.




Figure 4-26: Channel power settings

Occupied bandwidth

The occupied bandwidth is defined as the bandwidth that contains a specified percentage of the entire power of the transmitter. Default occupied bandwidth for the entire power of the transmitter is predefined at 99%. The following dialog provides the required measurement settings in the "Settings" tabs.




Figure 4-27: Occupied bandwidth settings

TDMA power

The TDMA (time division multiple access) power is measured in the time domain of the instrument. In the mobile radio standard like, e.g. GSM, several users share a channel and each user is assigned a period of time or timeslot for usage. With TDMA power measurement, you can determine the power over one of the timeslot. The following dialog provides the required measurement settings in the "Settings" tabs.

Settings

Resolution Bandwidth: 300000 Hz Auto Trace Detector: Auto Peak

Video Bandwidth: 1000000 Hz Auto Burst Length: 0.00047 s

Sweep Time: 0.001 s Auto

Figure 4-28: TDMA settings

Spectrum emission mask

The spectrum emission mask (SEM) measurement is a method used to detect the spurious emissions or intermodulation products of a signal. When performing the SEM measurement, the instrument checks the signal against a spectral mask to determine whether the signal complies with a specific standard. The following dialog provides the required settings to define the spectral mask in the "SEM" tab. The "Preview" tab illustrates the spectral mask defined in the "SEM" tab.

	Limit Check Mode	Range Start	Range Stop	RBW	Limit Start Abs (dBm)	Limit Stop Abs (dBm)	Limit Start Rel
1	Absolute	-12750000	-8500000	1000000	-49	-49	
2	Absolute	-8500000	-7500000	1000000	-49	-39	
3	Absolute	-7500000	-3500000	1000000	-39	-35	
4	Absolute	-3500000	-2500000	30000	-50	-35	
5	Ref Chan Power	-2500000	2500000	30000			
6	Absolute	2500000	3500000	30000	-35	-50	
7	Absolute	3500000	7500000	1000000	-35	-39	
8	Absolute	7500000	8500000	1000000	-39	-49	
9	Absolute	8500000	12750000	1000000	-49	-49	
10	None						
11	None						
12	None						
13	None						
14	None						

Figure 4-29: SEM settings

4.7.7 Using Quick Name Table



The "Quick Name Table" is only applicable for R&S FSC, R&S FSH4 and R&S ZVH product series.

The R&S InstrumentView comes with a predefined quick name table which provides a set of naming elements that can be used to create meaningful name in a faster and convenient manner. Using the "Quick Name Table" editor menu, you can customize the frequently used terms when compiling a filename. See ["Quick name table editor"](#) on page 56.

Quick name table editor

The "Quick Name Table" editor allows you to open, edit and save the quick name table. See [Figure 4-30](#).

1	2	3	4	5	6
1 Location	Site	RL	Sector	UL	450
2		IL	A	DL	700
3		VSWR	B		850
4		DTF	C	GSM	900
5		ISOL	D	UMTS	1800
6		POW	E	CDMA2000	1900
7		SPECTR		EVDO	2100
8		ACLR		LTE	
9				TD-SCDMA	
10					
11					
12					
13					
14					
15					
16					
17					
18					
19					
20					

② New
③ Open
④ Save

Figure 4-30: Quick name table editor

- 1 = Editor of the "Quick Name Table"
- 2 = "New" button creates a new quick name table for entry
- 3 = "Open" button loads an existing quick name table
- 4 = "Save" button saves the current quick name table

4.7.8 Using Analog Modulation Analysis AM Limits



The "Analog Modulation Analysis AM Limits" is only applicable for R&S FPH and R&S FPC product series.

Using the "Ama AM Limits" editor menu, you can customize the "Ama AM Limits" table which is used to evaluate the performance of the amplitude modulated signal. See [Figure 4-31](#).

Ama AM limits table editor

The "Ama AM Limits" table editor allows you to open, edit and save the Ama AM limits table . See [Figure 4-31](#).

Name

☰	Type	Enable	Upper limit	Unit	Enable	Lower Limit	Unit
	Carrier Freq Offset	<input type="checkbox"/>	9999999.9	Hz	<input type="checkbox"/>	-9999999.9	Hz
	Carrier Power	<input type="checkbox"/>	200	dBm	<input type="checkbox"/>	-200	dBm
	Modulation Index	<input type="checkbox"/>	100	%	<input type="checkbox"/>	0	%
	+Peak	<input type="checkbox"/>	① 999	%	<input type="checkbox"/>	0	%
	-Peak	<input type="checkbox"/>	0	%	<input type="checkbox"/>	-999	%
	±Peak/2	<input type="checkbox"/>	999	%	<input type="checkbox"/>	0	%
	RMS	<input type="checkbox"/>	999	%	<input type="checkbox"/>	0	%
	Mod. Freq	<input type="checkbox"/>	2000000	Hz	<input type="checkbox"/>	0	Hz
	SINAD	<input type="checkbox"/>	100	dB	<input type="checkbox"/>	-20	dB
	THD	<input type="checkbox"/>	20	dB	<input type="checkbox"/>	-100	dB

② ③ ④

Figure 4-31: Ama AM limits table editor

- 1 = Editor of the "Ama AM Limits" table
- 2 = "New" button creates an Ama AM limits table for entry
- 3 = "Open" button loads an existing Ama AM limits table
- 4 = "Save" button saves the current Ama AM limits table

4.7.9 Using Analog Modulation Analysis FM Limits



The "Analog Modulation Analysis FM Limits" is only applicable for R&S FPH and R&S FPC product series.

Using the "Ama FM Limits" editor menu, you can customize the "Ama FM Limits" table which is used to evaluate the performance of the frequency modulated signal. See [Figure 4-32](#).

Ama FM limits table editor

The "Ama FM Limits " table editor allows you to open, edit and save the Ama FM limit table . See [Figure 4-32](#).

Name <input type="text"/>							
Type	Enable	Upper limit	Unit	Enable	Lower Limit	Unit	
Carrier Freq Offset	<input type="checkbox"/>	9999999.9	Hz	<input type="checkbox"/>	-9999999.9	Hz	
Carrier Power	<input type="checkbox"/>	200	dBm	<input type="checkbox"/>	-200	dBm	
Frequency Deviation	<input type="checkbox"/>	2000000	Hz	<input type="checkbox"/>	0	Hz	
+Peak	<input type="checkbox"/>	2000000	Hz	<input type="checkbox"/>	0	Hz	①
-Peak	<input type="checkbox"/>	0	Hz	<input type="checkbox"/>	-2000000	Hz	
±Peak/2	<input type="checkbox"/>	2000000	Hz	<input type="checkbox"/>	0	Hz	
RMS	<input type="checkbox"/>	2000000	Hz	<input type="checkbox"/>	0	Hz	
Mod. Freq	<input type="checkbox"/>	400000	Hz	<input type="checkbox"/>	0	Hz	
SINAD	<input type="checkbox"/>	100	dB	<input type="checkbox"/>	-20	dB	
THD	<input type="checkbox"/>	20	dB	<input type="checkbox"/>	-100	dB	

② New ③ Open ④ Save

Figure 4-32: Ama FM limits table editor

- 1 = Editor of the "Ama FM Limits" table
- 2 = "New" button creates an Ama FM limits table for entry
- 3 = "Open" button loads an existing Ama FM limits table
- 4 = "Save" button saves the current Ama FM limits table

4.7.10 Wizard Set Editor



The "Wizard Set Editor" is not applicable for the R&S FSC product series.

Using the "Wizard Set Editor" menu, you can customize the measurement table list which consists of several datasets used to perform a specific instrument setting and measurements, for example frequency setting, power meter measurement, analog modulation measurement. To acquire a dataset, set up the instrument as per your requirement and save the configuration. You can also use one of the predefined datasets to customize the measurement table list.

For instrument setup using the R&S FSH4 or R&S ZVH, the editor provides additional selection for calibration method use in the wizard measurement. See the respective instrument user manual for the list of available calibration method.



The section for "Cable Definition for Antenna & Cable Test" is not available for instrument setup using the R&S FPC and R&S FPH.

The measurement table list forms the measurement sequence in the wizard set. See item 5 in [Figure 4-33](#)

For more information on dataset, see [Chapter 4.3, "Save Instrument"](#), on page 20.

Wizard

The "Wizard " editor allows you to open, edit and save the measurement wizard set. See [Figure 4-33](#).

To arrange the measurement sequence in the wizard set, double clicked or "Add" the desired dataset from the PC folder directory to the measurement table list. See index 4 and 5 of [Figure 4-33](#).









Figure 4-33: Wizard editor

- 1 = [Homepage icon](#)
- 2 = Opens the PC window explorer
- 3 = List of datasets that are available in the PC
- 4 = [Navigation icon](#) to preview, add, navigate and remove dataset in the measurement table list
- 5 = List of selected datasets used in the measurement table list. The "Name", "Instructions" and "Hardware_Setting" column are defined in the [Measurement Settings dialog](#).
- 6 = [Measurement settings tab](#)
- 7 = [Global dialog box](#)
- 8 = [Encryption dialog box](#)
- 9 = [Cable definition for antenna & cable test dialog box](#)
- 10 = "New" button creates a wizard set for entry
- 11 = "Open" button loads an existing wizard set entry
- 12 = "Save" button saves the current wizard set entry

Navigation icon

Navigation icon	Function
 View	Previews a selected dataset in the measurement table list.
 Add	Adds a selected dataset from the PC dataset list into the measurement table list.
 Up	Navigates upward in the measurement table list.
 Down	Navigates downward in the measurement table list.
 Remove	Removes a selected dataset from the wizard set.

Global

The "Global" dialog box provides the following settings that configure the wizard set:

- "Measurement Set Name"
Name of the measurement wizard set. This field is displayed in the instrument as a read-only parameter.
- "Description (Optional)"
Description of the measurement task. This field is displayed in the instrument as a read-only parameter.
- "Description / Measurement Font"
Font type for on-screen instructions (Latin, Chinese/Japanese and Korean fonts are supported).
- Default Calibration
Sets the default calibration method use during the wizard measurement. See the respective instrument user manual for the calibration method information.

- "Allow Variable Number of Sequence Steps"
If enabled, this field is configurable in the instrument and it allows you to remove steps from the measurement wizard set.
If not enabled, this field is displayed in the instrument as a read-only parameter.
- "Allow Skip Measurements & Finish Wizard Sequence"
If enabled, this field is configurable in the instrument and it allows you to skip the measurement step or finished the measurement wizard set.
If not enabled, this field is displayed in the instrument as a read-only parameter.

Encryption

The "Encryption" dialog box provides the encryption function to secure the edited measurement wizard set.

The encrypted wizard set is only visible in the instrument with serial number configured in the "Encryption" dialog.

To enable the "Encryption" dialog, activate the "Encryption Enabled" checkbox.

To limit the usage of the wizard set on a selective number of instruments, add the instrument serial number defined in the field of "Specific Serial Numbers".

Cable definition for antenna & cable test

The "Cable Definition for Antenna & Cable Test" dialog box configures the cable model and cable length used in the instrument antenna & cable test mode.

To enable a different cable characteristic after each individual measurement in a wizard sequence (such as to perform same measurement for different cables), enable the checkbox "Prompt User to Change Cable Settings".

Measurement settings

The "Measurement" tab configures the individual dataset used in the measurement table list.

Navigates from the list of datasets in the measurement table list (see index 5 of [Figure 4-33](#)) and select the desired dataset for configuration.

Defines the "Measurement Name" and describes the "Instructions" necessary for the measurement step.

Note: The description defined in the "Instructions" is displayed in the wizard message box during the execution of the wizard set. See index 2 of [Figure 4-35](#).




Figure 4-34: Measurement settings tab

- 1 = Defines the measurement name of the selected dataset
- 2 = Identifies the dataset filename that the measurement setting is linked to
- 3 = Defines the instruction description displayed in the wizard message box
- 4 = [Instruction picture dialog](#)
- 5 = Previews the configured measurement wizard dialog
- 6 = Hardware settings to configure the instrument's BNC input ("Trigger Input" or "Reference Input")

Instruction picture

The "Instruction Picture" section allows you to display a graphical image during the execution of the measurement wizard set. See [Figure 4-35](#).

To select the desired picture, select "Browse" button to open the PC window explorer and select the graphic image to use.

The "Preview" button allows you to preview the selected graphical image.




Figure 4-35: Wizard dialog box

1 = Instruction picture image
2 = wizard message box

4.7.11 Map Creator



Context Menu

Move the mouse scroll wheel to zoom in or zoom out on the map.



The "Map Creator" is only applicable for R&S FPH and R&S FSH4 product series.

The "Map Creator" menu allows you to create a customize map for the indoor mapping application in the instrument. The tool is divided into the map section and the setup section. The purpose of the tool is to generate a small archive of images including an IDM file for use on the instrument and in the maps workspace.

In addition to creating a map, you can also specify the exact geographical location of the area you are measuring. To do so, you can specify three GPS reference points in the entry field (see item 4 of [Figure 4-36](#)). With a GPS referenced map, it provides the following useful features:

- The map created is automatically rotated with the north side faces up.
- The instrument calculates and displays the distance between measurement points (in meters or feet, depending on the regional settings).

- You are able to embed the collected data into maps with a larger scale. Thus, you are able to, for example, combine measurement data recorded with the "Outdoor Mapping" application and data recorded with the "Indoor Mapping" application in a single map. For more information, see "Collecting Map Data chapter" in the user manual.





Figure 4-36: Map creator dialog box

- 1 = Map section
- 2 = Map folder name
- 3 = [GPS reference coordinate](#)
- 4 = Entry fields for the GPS reference coordinates.
- 5 = Load image supporting file format: ".png", ".bmp", ".tiff", ".gif", ".jpg"
- 6 = [Generate map](#)


GPS reference coordinates

This GPS reference coordinate allows you to create a georeferenced map (with GPS coordinates) or a non-geo-reference map (without GPS coordinates). When enabled, three GPS reference coordinate positions ("Latitude" and "Longitude") are required to enter in the setup section with reference of the GPS targets  shown on the map. You can move the GPS target on the map which represents the corresponding values of the GPS reference coordinates.


Generate map



When generating the map, the R&S InstrumentView deletes all existing content in the selected folder.



The generated map data consists of different zoom level of the images stored in separate folders, a PNG file of the image and an IDM file of the map data.



4.7.12 EMF Editor Tool

The EMF editor tool is used to configure the EMF measurement configuration file (EMCF) and the EMF definition file (EMDF). It consists of the EMF measurement set editor and EMF measurement configuration editor.

4.7.12.1 EMF Measurement Set Editor



Right-click in the measurement library table to access the following menus:

- "Edit" - Edits the selected measurement configuration file, it opens the measurement configuration editor, see [Chapter 4.7.12.2, "EMF Measurement Configuration Editor"](#), on page 70
- "Add" - Adds the selected measurement configuration file to the measurement set table
- "Delete" - Deletes the selected measurement configuration file from the measurement library path directory

Right-click in the measurement set table to access the following menus:

- "Up" / "Down" - Navigates the selected measurement configuration file up/down in the table
- "Remove" - Removes the selected measurement configuration file in the table

Vertical scrollbar

- See details in ["Context Menu"](#) on page 7.

Horizontal scrollbar

- See details in ["Context Menu"](#) on page 7.

The EMF measurement set editor is used to configure the EMF measurement definition file (*.emdf). The definition file consists the sequence order of one or more EMF measurement configuration files for execution. The following EMF measurement set editor illustrates the different sections to configure the EMF measurement definition file.




Figure 4-37: EMF measurement set editor

- 1 = Displays measurement library directory path
- 2 = "Refresh" button refreshes file content in the selected measurement library directory
- 3 = [Homepage](#)
- 4 = Opens the PC window explorer to set measurement library directory path
- 5 = List of EMF measurement configuration files
- 6 = [Measurement set navigator](#)
- 7 = List of currently configured measurement set
- 8 = [Overview tab](#)
- 9 = [Limits tab](#)
- 10 = New button resets all data and creates a measurement definition file for entry
- 11 = Open button loads an existing measurement definition file for entry
- 12 = Save button saves the currently configured measurement definition file

Table 4-6: Measurement set layout

Editor layout	Function
Measurement library table	The measurement library populates the table with EMF measurement configuration files (*.emcf) extracted from the selected "Measurement Library" path.
Measurement set table	<p>The EMF measurement set table provides a list of currently configured EMF measurement set. It displays the sequence order of individual EMF measurement configuration files. Each measurement configuration contains five inline controls which you can use to define the execution behavior:</p> <ul style="list-style-type: none"> • "Cycle": Provides a dropdown box to select "Time" or "Count". If selected as "Time", sub-measurements are individually executed for the specified minimum duration. If selected as "Count", sub-measurements are individually executed for a specified number of runs. • "Time [hh:mm:ss]": Defines the minimum amount of time each sub-measurement is executed for. • "Count": Defines the number of times each sub-measurement is executed for. • "Instruction": If instruction is set "Yes", an instruction popup box is displayed on the EMF receiver prior to the starting of this measurement. If instruction is set "No", the EMF receiver starts this measurement without showing an instruction. The instruction description is entered in the "Instruction for Operator" text box. • "Next Step": Provides a dropdown box to select "Auto" or "Manual". If selected as "Auto", the EMF receiver automatically proceeds to next step when this measurement is finished. If selected as "Manual", the EMF receiver holds before proceeding to the next step when this measurement is finished. During this time, you can analyze the last measurement result. <p>To navigate the table in the measurement set table, see Measurement set navigator.</p>
Overview setup	Provides an overview of the selected EMF measurement configuration file including the measurement-specific information. See Overview display and limit lines
Limits settings	Provides the limit setup for the selected EMF measurement configuration file in the measurement set table. See Overview display and limit lines .

Measurement set navigator

The measurement set navigator allows you to edit the sequence order in the EMF measurement set table.

Navigator	Function
Add	Adds the selected EMF measurement configuration file from the measurement library table.
Edit	Edits the selected EMF measurement configuration file in the measurement set table. For more information, see Chapter 4.7.12.2, "EMF Measurement Configuration Editor" , on page 70.
Up / Down	Moves up / down the selected EMF measurement file in the table.
Remove	Deletes the selected EMF measurement file from the table.

Overview display and limit lines

The "Overview" tab contains information regarding the entire EMF measurement set. It contains the general information and displays measurement-specific details of the measurement setup. The "Limits" tab allows you to define the limit settings used in the measurement set.



Limit Lines

The limit lines are always treated as upper limit settings. This means that values exceeding the specified boundaries may result in an exposure warning or failed measurement result.

Measurement Definition 1

Measurement Set Name: EMF Measurement Test Set

Measurement Set Description: Sample

Measurement Type: E-Field

▼ Limits 2

Limit Line 1: Gen. Public Limit Line (Upper)

Limit Line 2: Worker Limit Line (Upper)

UMTS_2100 3

▼ Setup

Name	UMTS_2100
Mode	WCDMA
Start Frequency	2.11568 GHz
Stop Frequency	2.16912 GHz
RBW	Auto
Channel Bandwidth	3.84 MHz
Trace Mode	Clear / Write
RF Attenuation	0 dB
Reference Level	140 dBµV/m

▼ Equipment

Antenna Factor	TSEMF-B1_typical
Axis	All
Cable Factor	0 dB

▼ Corrections

Extrapolation Factor	10 dB
Antenna Anisotropy	0 dB
Instrument Uncertainty	0 dB

Instruction for Operator 4

Continue to 2nd Measurement LTE mode switch

Limit Lines

Limit Line 1

Select Gen. Public Limit Line

Limit Line 2

Select Worker Limit Line

Figure 4-38: Overview and Limits Tab

- 1 = "Measurement Definition" provides general information of the EMF measurement definition file. See [Table 4-6](#)
- 2 = Limit line displays the upper limits settings. See "[Limit Lines](#)" on page 69
- 3 = Measurement-specific setup. See details in [Chapter 4.7.12.2, "EMF Measurement Configuration Editor"](#), on page 70
- 4 = Text box to set instructions

Parameters	Function
"Measurement Definitions"	Provides a text box to configure the name of the "Measurement Set Name". This name is used as a filename suggestion when saving a new EMF definition file. Provides a text box to configure the optional description of the measurement set. This description is visible on the EMF receiver after loading the measurement set. Selection of the "Measurement Type". Only "Electric Field" (E-field, field strength expressed in V/m or dBuV/m) is available. This setting determines the type of EMF measurement configuration that can be added in the measurement set table
"Limits"	Displays the limit line configured in the "Limits" tab. See Overview display and limit lines .
Measurement-specific information	Displays measurement-specific information configured in Chapter 4.7.12.2, "EMF Measurement Configuration Editor" , on page 70.
"Instruction for Operator"	Text box to set instructions for operator. When "Instruction" is enabled in the "Measurement Set" table, a popup box with the instruction is displayed on the EMF receiver prior to starting the measurement

4.7.12.2 EMF Measurement Configuration Editor

The EMF measurement configuration editor is used to configure the EMF measurement configuration file (*.emcf). The configuration file contains the information on the instrument settings, transducer factor for the equipment (antenna and cable) and also the necessary site-specific correction factor for the equipment and measurement.

Each measurement configuration file is made up of a list of center frequencies for measurement. Each center frequency represents a sub-measurement in the measurement configuration file.

EMF measurement modes

There are five types of "Measurement Mode" supported:

- "Spectrum": The field strength of the center frequency is used as EMF result value.
- "Channel Power": The channel power level is used as EMF result value.
- "3GPP WCDMA": The P-CPICH signal power is used as EMF result value.
Up to 10 strongest scrambling code signal strength results per sub-measurement.
- "LTE-FDD": The power display (displayed cell property) is used as EMF result value. The possible power display modes are PSYNC, SSYNC, RSRP and RSPWR (default).
Up to 8 strongest cell ID signal strength results per sub-measurement.
- "TD-LTE": The power display (displayed cell property) is used as EMF result value. The possible power display modes are PSYNC, SSYNC, RSRP and RSPWR (default).
Up to 8 strongest cell ID signal strength results per sub-measurement.

See also [Table 4-8](#).




Figure 4-39: EMF measurement configuration editor

- 1 = "Measurement Configuration" provides general information of the configuration file. See [Table 4-7](#)
- 2 = Availability of acquisition settings depends on the selected "Measurement Type" and most settings are not editable. See [Table 4-8](#)
- 3 = Only compatible dataset can be imported to the "Acquisition Configuration". See [Table 4-8](#)
- 4 = Sub-measurement contains a list of center frequencies for execution
- 5 = Equipment tab provides control settings such as antenna and cable transducer factors
- 6 = Correction tab provides settings for site-specific correction factor for equipment and measurements
- 10 = New button resets all data and creates a measurement configuration file for entry
- 11 = Open button loads an existing measurement configuration file for entry
- 12 = Save button saves the currently configured measurement configuration file

Table 4-7: Measurement configuration layout

Parameters	Function
Measurement Configurations	Provides settings of the EMF measurement modes . Provides a text box to configure "Measurement Name". This name is used as a filename suggestion when saving a new EMF measurement configuration file. Selection of the "Measurement Type". Only Electric Field (E-field, field strength expressed in V/m or dBuV/m) is available.
Acquisition Configurations	Availability of the acquisition settings depends on the selected EMF measurement modes . For details on the acquisition settings, see the respective user manual for information. See also information on Table 4-8 .


Parameters	Function
Sub-Measurements	<p>Contains a list of center frequencies for execution. Each center frequency in the frequency list represents a sub-measurement. The amount of sub-measurement that can be added to the frequency list is limited based on the selected measurement mode:</p> <ul style="list-style-type: none"> • Spectrum and channel measurement: Up to 99 sub-measurements • WCDMA: Up to 10 sub-measurements • LTE-FDD and TD-LTE: Up to 10 sub-measurements <p>Each sub-measurement can be added by the followings:</p> <ul style="list-style-type: none"> • Inserting a single center frequency within the frequency list • "Generate Frequencies": Adding a range of center frequencies with a fixed "Step Width" in Hertz • "Generate Channel Numbers": Adding a range of center frequencies by specifying a channel table and providing the channel range. <p>You can remove a single or multiple center frequencies from the frequency list.</p>
Equipment settings	<p>Contains the controls regarding the equipment settings such as antenna and cable transducer factors.</p> <p>You can specify an antenna transducer factor such as primary (*.pritrtd) or an isotropic transducer file (*.isotrd) at the window browser dialog (e.g. file types). The Y-unit of the transducer file must be compatible with the selected measurement type. If the unit is not compatible, the file is rejected and error message is displayed.</p> <p>You can also define the antenna's direction of measurement ("X", "Y", "Z" or "X/Y/Z (All)") and the MIMO configuration for LTE measurement ("SISO Over The Air", "MiMO 2x2 Over The Air", "MiMO 4x4 Over The Air")</p> <p>Cable attenuation can be specified by either using a constant value (dB) or using a secondary transducer file (*.sectrd).</p> <p>For viewing the response of the transducer file, see Preview transducer table.</p>
Corrections	<p>Defines the site-specific correction factors for equipment and measurements.</p> <p>You can set the antenna anisotropy (correction made for any deformities in all orientation of an isotropic antenna for incoming waves) and instrument uncertainty in dB level.</p> <p>For measurement type selected for WCDMA, LTE-FDD and TD-LTE, an additional extrapolation factor is available for correction. It can either set as dB or as a dimensionless linear value.</p> <p>For measurement type selected for LTE-FDD, you can also make correction factor for "Time Division Duplex" in dB.</p>

Table 4-8: Relation between configurable dataset settings and measurement modes

Measurement mode	Resolution bandwidth	Video bandwidth	Span	Channel bandwidth ¹	Trace mode ¹	Power display ¹	Detector	RF Attenuation	Reference level
Spectrum	✓	✓	✓		✓		✓	✓	✓
Channel Power	✓	✓	✓	✓	✓		✓	✓	✓
3GPP WCDMA	✓			✓	✓			✓	✓
LTE-FDD	✓			✓	✓	✓		✓	✓
TD-LTE	✓			✓	✓	✓		✓	✓

¹Configurable dataset settings

4.8 Analyze the Instrument Dataset



The "Analysis" menu allows you to perform data analysis for instrument data collected from spectrogram, map measurement and EMF measurement results. It also allows you to export GPX file to KMZ and CSV file format.

- [Spectrogram](#).....73
- [Map Analysis](#).....77
- [GPX Conversion](#).....79
- [Dataset Image](#).....81
- [EMF Measurement Result](#).....82

4.8.1 Spectrogram



Spectrogram is only applicable for R&S FPH, R&S FSC, R&S FSH4 and R&S ZVH product series.



Context menu

Right-click on the spectrogram, vertical scrollbar or spectrum to access the following menus:

Spectrogram

- "Set time marker 1 here", "Set time marker 1 here" - Displays a vertical blue line in the spectrogram.


Vertical scrollbar

- See details in "[Context Menu](#)" on page 7.

Spectrum


- "Reset Zoom", "Reset Move" - Resets the spectrum display to original zoom level or position.

The spectrogram provides a workspace to analyze the spectrogram which is also known as long time recording. The workspace is divided into five sections, each providing specific information and or means to analyze the spectrogram data further.



- 1 = Compression spectrogram
- 2 = Spectrogram section
- 3 = Spectrum section
- 4 = Measurement section
- 5 = Selects "Open" button to load the spectrogram file
- 6 = Setup section

Compression spectrogram




The compressed spectrogram displays a compressed overview of the recorded spectrogram data. In the compressed spectrogram view, a selected line is displayed showing the location of the part that is currently displayed in the spectrogram and the spectrum section. You can use the mouse to move the line in the compressed spectrogram to analyze the data in the spectrogram.

You can right-click on the compressed spectrogram to set the current line as reference value. When using the current line as a reference, the reference is subtracted from all the records in the compressed spectrogram and the color spectrum changed accordingly. You can also right-click on the scroll bar to display the different scrolling options to navigate the data in the compressed spectrogram view.

Upon loading the next spectrogram, the R&S InstrumentView will prompt you to save the generated compressed spectrogram file.

Spectrogram section

The spectrogram section shows a part of the recorded spectrogram in the highest time resolution, e.g. one line in a spectrogram file represents in one sweep on the spectrum section. You can change the spectrogram frequency resolution by holding the CTRL key and moving the mouse scroller in the spectrum view. For more information on the mouse behavior, see Table 4-9. The amplitude of the signal in the spectrogram view is displayed in color spectrum according to the configuration setup in the "Color Setup" dialog box "Setup section" on page 76.






- 1 = Displays of color table
- 2 = Spectrogram section
- 3 = Displays of marker 1 line
- 4 = Displays of marker 2 line
- 5 = Context menu for spectrogram
- 6 = Scroll bar
- 7 = Displays of T1 time-line
- 8 = Left-click on the mouse to display of current selection line. This line is synchronized to the information displayed in the compressed spectrogram and spectrum section.
- 9 = Context menu for vertical scrollbar
- 10 = Displays of T2 time-line
- 11 = Indication of the spectrogram filename loaded

Spectrum section

The spectrum shows the spectrum at the current selected line in the spectrogram view. The spectrogram shows the amplitude as colors, the spectrum view shows the amplitude as Y deflection in the graph. It is possible to move the markers display, change and move the zoom area of the spectrum display by using the mouse. For more information on the mouse behavior, see [Table 4-9](#)




Table 4-9: Mouse behavior in spectrum section

Mouse behavior	Function
	Positions the mouse icon over the marker line until the icon display changed. Hold and left-click on the mouse and drag to move the marker display.
	Positions the mouse icon anywhere on the spectrum view, hold the CTRL key and move the mouse scroller to change the frequency resolution of the spectrum and spectrogram display.
	Positions the mouse icon over the spectrum display until the icon display changed. Left-click and hold on the mouse key to change the spectrum position.

Measurement section

The measurement section consists of three subsections:

- Measurement setup
The measurement setup contains all the setup properties required for specific measurement. The data displayed in this section is the same as the [spectrum section](#).
- Frequency maker
The data displays in the frequency marker corresponds to the settings in the "Marker Setup" configured in the [setup section](#).
- Time marker
The time markers section is used to display the time marker value and results as positioned in the [spectrogram section](#).



Setup section

The Setup section consists of two sections:

- Viewer setup
The viewer setup allows you to configure the display view ("Time", "Frequency markers" and "Time markers") in the spectrogram section and define the maximum reference level and range different for the color table. Using the "Auto range" function, you can automatically adjust the maximum reference level and the range different of the color table for optimum display. For more information, see "Working with the Spectrogram Result Display" in the user manual.

The screenshot shows a control panel with two main sections: 'Color Setup' and 'Show'.
Under 'Color Setup':
- 'Offset' is a numeric input field with the value '-41' and up/down arrow buttons.
- 'Range' is a numeric input field with the value '50' and up/down arrow buttons.
- There are two buttons: 'Auto range' and 'Reset'.
- 'Color table' is a dropdown menu showing a color gradient from blue to red.

Under 'Show':
- 'Time in spectrogram' is checked with a blue checkmark.
- 'Frequency markers' is checked with a blue checkmark.
- 'Time markers' is checked with a blue checkmark.

- Marker setup
For more information, see "[Marker Setup](#)" on page 26.

4.8.2 Map Analysis



Map is only applicable for R&S FPH, R&S FSC and R&S FSH4 product series.

The "Map Analysis" menu allows you to view maps and overlay it with the signal strength level from the GPX file. The "Map Analysis" workspace is divided into the map section and the setup section.

1 = Map section

2 = GPX position ("X (Pixels)", "Y (Pixels)") of the measurement

3 = Indices of the measurement

4 = Signal strength level of the measurement

5 = Selects "Load Map" to open file browser to search for IDM or PRJ map file

6 = Selects "Load GPX" to load the GPX file

7 = Legend of the color spectrum used for signal strength level

8 = Color settings dialog

9 = Enables / disables the display of GPX index on the map

10 = Enables / disables the display of signal strength level on the map

11 = GPX list loaded from the GPX file. The highlighted GPX list is shown blinking on the map.


12 = Positions the legend on the exported image

13 = Selects "Export Image" to file format (*.png, *.gif, *.bmp, *.jpg, *.tiff, *.tif)

14 = Exports the "GPX List" to CSV format

Color settings

The color settings dialog allows you to select the color representing the signal strength level to display on the map. After the configuration, the legend of the color spectrum reflects the color changes accordingly.






Figure 4-40: Color settings dialog

4.8.3 GPX Conversion



GPX conversion is only applicable for R&S FPH, R&S FSC and R&S FSH4 product series.



Context Menu

Right-click on the GPX list to access the following menus:

- "Include All" - Includes all the GPS coordinates in the GPX list
- "Exclude All" - Excludes all the GPS coordinates in the GPX list

The "GPX Conversion" provides a workspace where you can merge different GPX files into a single collection of measurement list and export the merge GPX data to KMZ or CSV file format. You can then edit the data within this collection by adding "Name" and "Description". Furthermore, you can also modify the colorized representation of the GPS positions for use in Google Maps.

The tool is divided into the grid section and setup section.




Figure 4-41: GPX conversion dialog box

- 1 = Checkbox to include or exclude the measurement indices in the CSV or KMZ file
- 2 = GPS position of the measurement ("Latitude" and "Longitude")
- 3 = Measured result of the measurement
- 4 = Editable field ("Name" and "Description")
- 5 = Load GPX file with valid GPS coordinates
- 6 = [Color setting dialog](#)
- 7 = Default indicator determines the preferred visible measurement when multiple measurements are grouped at a certain zoom level ("Best", "Average", "Worst")
- 8 = "Maximum Zoom Distance" determines the number of zoom layers stored in KMZ file. A higher zoom distance means fewer zoom layers and vice versa
- 9 = Checkbox to enable or disable the display of measurement indices on the map
- 10 = GPX files list table
- 11 = Checkbox to auto-open the KMZ file in Google Earth after creation
- 12 = Converts the GPX file list to KMZ file format
- 13 = Exports the GPX file list to CSV file format
- 14 = Context menu in GPX list

Color setting dialog

You can define the different color used to represent the level measured at the GPS position. Available colors for selection:

- "Magenta"
- "Light Blue"
- "Cyan"
- "Green"
- "Yellow"
- "Red"

4.8.4 Dataset Image



Context Menu

Right-click on the trace window to access the following menus:

- "Show measurement setup" - If enabled, the instrument settings and trace data are displayed below the screenshot. See [Figure 4-16](#).
- "Copy to clipboard" - If enabled, the dataset image with instrument settings and trace data are copied to the clipboard.

The "Dataset Image" menu is used to view screenshot embedded in the saved dataset with the optional display of measurement settings (if enabled).

This is a useful feature which allows the viewing of dataset image before activating dataset file from PC to the instrument. See [Chapter 4.6.9, "Activate Dataset to Instrument"](#), on page 43




Figure 4-42: Dataset image with measurement settings

- 1 = Dataset image
- 2 = Measurement settings

4.8.5 EMF Measurement Result



Context Menu

Right-click in the measurement table to access the following items:

- "Copy Data" - copies all data in the measurement list to the clipboard as comma-separated values (e.g. Excel).
- "Copy Graphics" - copies the bar chart graph to the clipboard.

Vertical scrollbar

- See details in "Context Menu" on page 7.

Horizontal scrollbar

- See details in "Context Menu" on page 7.

The EMF analysis workspace allows you to analyze and export EMF measurement results stored in the EMF result files (EMRF). You can analyze the measurement set and the sub-measurements results. The result values in the measurement set are presented in the following:

- Result: result value per center frequency, cell ID or scrambling code presented in "Sub-Measurement" tab
- Subtotal: sum of all sub-measurement results presented in "Measurement" and "Sub-Measurement" tab
- Total: sum of all totals of all measurements presented in "Measurement" tab

The screenshot displays the R&S InstrumentView software interface. On the left, the 'Measurements' tab shows a table with two rows of data:

Measurement	Field Strength	Exposure 1 (%)	Exposure 2 (%)	Peak Value
1 LTE_FDD_800_1800	2.97 mV/m	679.01 µV/m
2 LIMITS_2100	214.71 mV/m	579.48 µV/m

Below the table is a bar chart showing field strength for each measurement. The 'Total' value is 214.74 mV/m. On the right, the 'Sub-Measurements' tab shows a detailed table:

Frequency	Cell ID	Field Strength	Limit 1 (V/m)	Limit 2 (V/m)	Exposure 1 (%)	Exposure 2 (%)	Cycles
1 796.0000 MHz	445	2.04 mV/m	22
2 796.0000 MHz	444	340.14 µV/m	22
3 796.0000 MHz	446	262.41 µV/m	22
4 796.0000 MHz	331	358.18 µV/m	22
5 796.0000 MHz	343	289.22 µV/m	22
6 796.0000 MHz	347	125.69 µV/m	22
7 806.0000 MHz	42	170.38 µV/m	32
8 806.0000 MHz	238	16.23 µV/m	32
Subtotal:		2.97 mV/m

Below this table is a bar chart showing field strength for each sub-measurement. The interface also includes a central settings panel with tabs for 'Overview', 'Setup', and 'Export', and various configuration options for the measurement setup.

- 1 = Measurement results including measurement totals. Results are presented in data grid and are visualized using a bar chart
- 2 = Sub-measurement results per center frequency and scrambling code or cell ID, including measurement subtotals. Results are presented in a data grid and are visualized using a bar chart.
- 3 = Measurement header
- 4 = Measurement result table
- 5 = Measurement result bar chart
- 6 = Overview tab containing global measurement set information and measurement-specific data
- 7 = Setup tab contains controls which affect all measurements in the measurement set
- 8 = Export tab containing result export options
- 9 = Sub-measurement header
- 10 = Sub-measurement result table
- 11 = Sub-measurement result bar chart
- 12 = Open button loads an existing EMRF file
- 13 = Save button saves post measurements corrections and limits in the EMRF file (*.emrf)
- 14 = Reset button reverts corrections and limits to how they were originally specified
- 15 = Copy button copies CSV data of the measurement to the operating system clipboard
- 16 = Export button exports the available data into a report

Table 4-10: Details of measurement and sub-measurement results tab

Parameters	Function
Measurement header	Displays the name of the selected measurement following by the result mode (Avg, Max, Min, RMS) in which the results are presented. Displays the measurement start time, stop time and measurement duration (stop time - start time).
Measurement result table	Overview of the available results of all measurements in the EMF measurement set. It displays the subtotal results of the sub-measurements ("Field Strength", "Exposure 1 (%)", "Exposure 2 (%)") and the total sum results of these subtotal values for all measurements. The "Peak Value" displays the maximum single value of the field strength measurement.
Measurement result bar chart	Visual display of the measurement result (field strength) of all the measurement set. A marker line is placed on the selected measurement to quickly identify the exact field strength on the bar chart.
Sub-measurement header	Displays the selected sub-measurement result mode (Avg, Max, Min, RMS) in which the results are presented. Displays the measurement start time, stop time and measurement duration (stop time - start time).
Sub-measurement result table	Detailed displays of the selected measurement. The sub-measurement contains a list of measurements (Field Strength, Limit 1 (V/m), Limit 2 (V/m), Exposure 1 (%), Exposure 2 (%)) on frequencies configured in the selected measurement including a subtotal sum of "Field Strength", "Exposure 1 (%)" and "Exposure 2 (%)". Note: Limit 1 (V/m), Limit 2 (V/m) can be configured in the "Setup" tab. Depending on the selected measurement mode , additional parameters of "Scrambling Code" or "Cell ID" is displayed. The "Cycles" shows the number of runs the sub-measurement was executed.
Sub measurement result bar chart	Visual display of the sub-measurement result (field strength). A marker line is placed on the selected measurement to quickly identify the exact field strength on the bar chart.

Overview

The "Overview" tab contains information regarding the entire measurement, it includes the general information, limit lines results and measurement-specific details of the selected measurement.

For more information on the measurement-specific details, see [Chapter 4.7.12.1, "EMF Measurement Set Editor"](#), on page 66 and [Chapter 4.7.12.2, "EMF Measurement Configuration Editor"](#), on page 70.

The screenshot shows the 'EMF' overview dialog with three numbered callouts:

- 1**: General information for the measurement set.

Start Date	5/11/2018
Stop Date	5/14/2018
Start Time	01:24 PM
Stop Time	08:58 AM
GPS Latitude	---
GPS Longitude	---
Duration	02:19:34:15
- 2**: Displays limit line details and limit test result.

Limit Line 1	ICNIRP_GP (Upper)
Result Limit Line 1	PASS
- 3**: Displays of measurement-specific details reflected from settings.

WC meting	
Setup	
Name	WC meting
Mode	WCDMA
Start Frequency	2.11568 GHz
Stop Frequency	3.10192 GHz
RBW	Auto
Channel Bandwidth	3.84 MHz
Trace Mode	Clear / Write
RF Attenuation	0 dB
Reference Level	140 dBμV/m
Equipment	
Antenna Factor	TS-EMF_Example
Axis	All
Cable Factor	TSEMFZ2 example
Corrections	
Antenna Anisotropy	<input type="text" value="1"/> dB
Instrument Uncertainty	<input type="text" value="2"/> dB
Extrapolation Factor	<input type="text" value="3"/> dB
=	
	<input type="text" value="2"/> Lin

Figure 4-43: Overview tab dialog

- 1 = General information for the measurement set
- 2 = Displays limit line details and limit test result
- 3 = Displays of measurement-specific details reflected from settings in [Chapter 4.7.12.1, "EMF Measurement Set Editor"](#), on page 66 and [Chapter 4.7.12.2, "EMF Measurement Configuration Editor"](#), on page 70

Table 4-11: Details of overview tab

Parameters	Function
General information	Displays start date, start time, stop date, stop time and measurement duration of the selected measurement. Displays the GPS latitude and longitude reading.
Limit Lines	Displays the selected limit lines from the setup tab. It also displays the global pass / fail limit lines test result. If a single sub-measurement's field strength result exceeds the interpolated limit at that specific frequency, the limit result is considered failed. "Exposure Ratios" below 100%, indicates a passed limit result
Measurement-specific details	The measurement-specific details reflect the settings from Chapter 4.7.12.1, "EMF Measurement Set Editor" , on page 66 and Chapter 4.7.12.2, "EMF Measurement Configuration Editor" , on page 70. The parameters in "Setup" and "Equipment" sections are read-only parameters. The parameters in "Corrections" section can be overwritten and the settings affect the results in both "Measurements" and "Sub-Measurements" tab. Note: "Extrapolation Factor" - Only applicable for "3GPP WCDMA", "LTE-FDD" and "TD-LTE" measurement mode. Note: "Time Division Duplex" - Only applicable for "TD-LTE" measurement modes.

Setup tab

The "Setup" tab contains controls affect all measurements in the measurement set.

For details on the affected parameters, see [Chapter 4.7.12.1, "EMF Measurement Set Editor"](#), on page 66, [Chapter 4.7.12.2, "EMF Measurement Configuration Editor"](#), on page 70 and [Overview](#).





Figure 4-44: Setup tab dialog

Parameters	Function
Presentation	<p>Sets the result mode in the measurement set. Available result modes are: "Average", "RMS", "Maximum" and "Minimum".</p> <p>By default, result mode is set to "RMS".</p>
Units	<p>Sets the field strength unit in the measurement set:</p> <ul style="list-style-type: none"> E-Field measurement sets - dBuV/m, V/m and W/m². <p>Sets the "Exposure Ratio (ER)" unit: Available units are E² / L², %, ‰ and PPM (parts per million).</p>
Limit Lines	<p>Defines the limit lines using limit line files. The Y-Unit of the limit line file must be compatible with the selected field strength unit. If unit is not compatible, the file is rejected and an error message is displayed.</p> <p>Selects the  to discard limit line selection.</p>

Export tab

The "Export" tab contains controls which determine the content and format of reports for exporting. Selects the checkbox "Open after Generation" to open report file after exporting the report.

Report Content

Average Results Max Results


RMS Results Min Results

General Information Measurement Settings


Data Tables Graphics

Logos

Frontpage Logo User Logo ▼

 Select No Logo Selected

Footer Logo R&S Logo ▼



Output Options

Language English ▼ Format PDF ▼

Open after Generation

Figure 4-45: Export tab dialog

Table 4-12: Details of export tab

Parameters	Function
Report content	<p>Selection of result mode to be presented in the report. Available selections are Average, RMS, Max and Mini results.</p> <p>Selection of the details to be presented in the report. Available selections are "General Information", "Data Tables" for sub-measurement results, "Measurement Settings " for measurement-specific details and "Graphics" presentation.</p>
Logo	Selection of logo file used in the front page and footer of the report.

4.9 Options



The "Options" menu allows you to configure the application preference such as the color settings of the trace element, selection of instrument type family, directory path setting , display of keyboard shortcuts and software information.

- [Color Settings](#).....88
- [Directory Settings](#).....90
- [Application Settings](#).....91
- [Keyboard Shortcuts](#).....92
- [Command-Line Tool](#).....92
- [About](#).....93

4.9.1 Color Settings

The "Color Settings" dialog provides settings for the color displayed on the different trace elements in the trace window. See [Figure 4-46](#).

The following settings are provided:

- Background
- Grid line
- Text display on the trace window
- Up to four trace lines
- Up to four memory trace lines
- Up to four maximum trace lines
- Up to four minimum trace lines
- Up to four average trace lines
- Indicator line
- Display line
- Marker and delta marker line
- Upper and lower limit line
- Tx and adjacent channel indicator

- Channel bandwidth




Figure 4-46: Color settings dialog

1 = "Color Settings" menu displays each trace element color in the trace window

2 = "Preview" window displays each trace element color in the trace window

Select the desired trace element in the "Color Settings" menu and the "Color selection" dialog is displayed for configuration. See [Figure 4-47](#).

There are a few ways to change the color settings in the "Color Selection" dialog:

- Selects the desired color settings in the color display area
- Selects the desired brightness setting in the brightness level indicator
- Modifies the RGB color codes
- Modifies the Hex color codes




Figure 4-47: Color selection dialog

- 1 = Color display area
- 2 = Brightness settings indicator
- 3 = Color preview area
- 4 = RGB color codes
- 5 = HEX color codes

Select the "Default" button to restore the default settings of the trace element color. See [Figure 4-46](#).

4.9.2 Directory Settings

The "Directory Settings" dialog provides the list of default path directories setting for the different type of files used in the application.

To change the path directories setting, double-click the desired file type to configure the directory setting.

Upon selection, the "Browse For Folder" dialog is displayed to configure the path directory setting. See [Figure 4-48](#).




Figure 4-48: Directory settings dialog

- 1 = List of the different file types directory setting
- 2 = Selects "Default" button to reset the path directory to default settings
- 3 = Selects "OK" button to confirm the settings of the path directory
- 4 = Selects "Cancel" button to exit the path directory settings
- 5 = File browser for path directory selection


4.9.3 Application Settings

By default, the calibration data (if applicable) is not included in the saved dataset.

To retrieve the full dataset, enable the checkbox to retrieve the full dataset including the calibration data when applicable.

By default, the "Network disconnect detection" status is checked. When enabled, the R&S InstrumentView reflects the network connection status accordingly. See [Table 3-1](#).

The length unit displays the desired unit shown in the calibration data (if applicable).



4.9.4 Keyboard Shortcuts

There are several shortcut keys that you can use to navigate in the application.




Figure 4-49: Shortcut keyboard

4.9.5 Command-Line Tool



Command-line tool is only applicable for R&S ZVH & R&S ZPH product series.

The command-line tool is run via the command prompt supported by PC's running Windows 7, 8 and 10.

The tool supported two types of command:

- ConvertToZPH
Convert individual dataset or datasets in a directory to compatible dataset of the desire device type.

Example: Example syntax for the ZVH -> ZPH converter:

```
InstrumentView.exe -ConvertToZPH "input.set" "output.set"
```

```
InstrumentView.exe -ConvertToZPH "inputDirectory" "outputDirectory"
```

- ConvertToCSV
Convert individual files to CSV compatible format

Example: Example syntax for the Dataset -> .CSV converter:

```
InstrumentView.exe -ConvertToCSV "input.set" "output.csv"
```

4.9.6 About

See "[About the software information](#)" on page 5.

Index

A

AMA AM limits	57
Analysis	
Dataset image	73
EMF measurement result	73
GPX conversion	73
Map analysis	73
Spectrogram	73

C

Cable models	47
Calibration kits	48
Channel table	51
Connecting the instrument	
LAN	10
USB	10
Customizing test report	17

E

Editor	45
Instrument datasets	45
EMF measurement configuration editor	65
EMF measurement modes	70
Relation between configurable dataset settings and measurement modes	70
EMF measurement result	82
EMF measurement set editor	65

F

FM limits table	58
-----------------------	----

I

Installing R&S InstrumentView	
Installing the R&S InstrumentView software	5
R&S InstrumentView software information	5
Running the R&S InstrumentView software	5
Instrument	29
Active dataset to instrument	29
Date time synchronization	29
File transfer	29
Lab display	29
Multi-transfer	29
Remote display	29
Save dataset from instrument	29
Screenshot	29
Synchronization	29
Instrument datasets	
AM limits	45
Cable models	45
Calibrations kits	45
Channel table	45
EMF editor	45
FM limits	45
Limit line	45
Map creator	45
Quick name table	45
Standards	45
Transducers	45
Wizard sets	45

M

Map creator	63
Measurement type	
Channel power	53
Occupied bandwidth	53
Spectrum emission mask	53
TDMA power	53

O

Open dataset	22
Options	88
Color settings	88
Command-line tool	88
Directory settings	88
Instrument type selection	88
Keyboard shortcuts	88

P

Preview	15
Printing	15

Q

Quick name table	56
------------------------	----

R

R&S InstrumentView screen layout	7
--	---

S

Save dataset	20
--------------------	----

T

Trace window	
Add trace	22
Get trace	22

U

Using limit lines	49
Limit lines table	49
Preview	49
Using R&S InstrumentView	15
Using standards	52
Measurement type	52
Standards table	52
Using transducers	45
Preview	45
Transducers table	45

W

Wizard set editor	58
-------------------------	----