

This user's manual explains how to install the 91030 USB communication adaptor driver. To ensure correct use, please read this manual thoroughly before operation. Keep this manual in a safe place for quick reference.

1st Edition: June 2018 (YMI)
All Rights Reserved, Copyright © 2018, Yokogawa Test & Measurement Corporation



IM 91030-02Z2
1st Edition


Operating System

Windows 7 (32 bit/64 bit), Windows 8 (32 bit/64 bit), Windows 8.1 (32 bit/64 bit), Windows 10 (32 bit/64 bit)


Installation Procedure

Install the USB driver from the CD provided with this instrument in the PC. The following procedure explains how to install the software on Windows 10.


1. Load the CD into the PC's CD drive.
2. Connect this instrument's USB plug (USB type A) to the PC.
3. Open Device Manager from Control Panel.




4. Under Other devices, right-click MODEL 91030. This only appears when 91030 is connected to the PC.




5. Click Update Driver Software. A driver software update window appears.




6. Click Browse my computer for driver software. A folder browsing window appears.




7. Select the Include subfolders check box, and click Browse.
8. Select the CD drive.
9. Click OK. The installation begins. If an installation confirmation message appears during the installation, confirm to continue the installation. Installation is complete when the following window appears.




10. In Device Manager of Control Panel, check that "MODEL 91030" is displayed under "Universal Serial Bus controllers."



11. Under Other devices, right-click USB Serial Port.



12. Click Update Driver Software. A driver software update window appears.
13. Repeat steps 6 to 9. When the installation is complete, in Device Manager of Control Panel, check that "MODEL 91030" is displayed under "Ports (COM & LPT)."



Uninstallation Procedure

If you need to reinstall the driver, uninstall the driver first.

1. Connect this instrument's USB plug (USB type A) to the PC.
2. Open Device Manager from Control Panel.
3. Under Universal Serial Bus controllers, right-click MODEL 91030.
4. Select Uninstall. The driver will be uninstalled.
5. Under Ports (COM & LPT), right-click MODEL 91030.
6. Select Uninstall. The driver will be uninstalled.

User's Manual Model 91030 USB 通信アダプタ用ドライバ インストールマニュアル

このユーザズマニュアルは、91030 USB 通信アダプタ用ドライバのインストール方法について説明しています。
ご使用前にこのマニュアルをよくお読みいただき、正しくお使いください。お読みになったあとは、ご使用時にすぐにご覧になれるところに、大切に保管してください。

1st Edition: June 2018 (YMI)
All Rights Reserved, Copyright © 2018, Yokogawa Test & Measurement Corporation

YOKOGAWA

IM 91030-02Z2
初版


対応 OS

Windows 7(32bit/64bit)、Windows 8(32bit/64bit)、
Windows 8.1(32bit/64bit)、Windows 10(32bit/64bit)


インストール方法

本機器に付属されている CD 内の USB ドライバを、PC にインストールします。
以下は、Windows 10 でインストールするときの操作です。


1. CD を PC の CD ドライブに挿入します。
2. 本機器の USB プラグ (USB タイプ A) を PC に接続します。
3. コントロールパネルからデバイスマネージャーを開きます。




4. 「ほかのデバイス」にある「MODEL 91030」を右クリックします。
PC に 91030 を接続していないと表示されません。



5. 「ドライバソフトウェアの更新」を選択します。
ドライバソフトウェアの更新画面が表示されます。




6. 「コンピューターを参照してドライバソフトウェアを検索します」を選択します。
フォルダーの参照画面が表示されます。




7. 「サブフォルダーも検索する」をチェックし、「参照」をクリックします。
8. CD ドライブを選択します。
9. 「OK」をクリックします。インストールが開始されます。
インストール途中にインストールを確認するメッセージが表示された場合は、インストールを継続するように操作してください。
下記の画面が表示され、インストールが終了します。




10. コントロールパネルのデバイスマネージャーの「ユニバーサルシリアルバスコントローラ」に、「MODEL 91030」が表示されることを確認してください。



11. 「ほかのデバイス」にある「USB Serial Port」を右クリックします。



12. 「ドライバソフトウェアの更新」を選択します。
ドライバソフトウェアの更新画面が表示されます。
13. 前述の操作 6~9 と同様に操作します。
インストールが完了し、コントロールパネルのデバイスマネージャーの「ポート (COM と LPT)」に、「MODEL 91030」が表示されることを確認してください。



アンインストール方法

ドライバをインストールしなす場合は、一度、ドライバをアンインストールします。

1. 本機器の USB プラグ (USB タイプ A) を PC に接続します。
2. コントロールパネルからデバイスマネージャーを開きます。
3. 「ユニバーサルシリアルバスコントローラ」にある「MODEL 91030」を右クリックします。
4. 「削除」を選択します。ドライバがアンインストールされます。
5. 「ポート (COM と LPT)」にある「MODEL 91030」を右クリックします。
6. 「削除」を選択します。ドライバがアンインストールされます。